

Package ‘Pareto’

March 3, 2021

Type Package

Title The Pareto, Piecewise Pareto and Generalized Pareto Distribution

Version 2.4.2

Description Utilities for the Pareto, piecewise Pareto and generalized Pareto distribution that are useful for reinsurance pricing. In particular, the package provides a non-trivial algorithm that can be used to match the expected losses of a tower of reinsurance layers with a layer-independent collective risk model. The theoretical background of the matching algorithm and most other methods are described in Ulrich Riegel (2018) <doi:10.1007/s13385-018-0177-3>.

License GPL (>= 2)

Encoding UTF-8

LazyData true

RoxygenNote 7.1.1

VignetteBuilder knitr

Depends R (>= 2.10)

Suggests testthat, knitr, rmarkdown, lpSolve

URL <https://github.com/ulrichriegel/Pareto#pareto>

Language en-US

NeedsCompilation no

Author Ulrich Riegel [aut, cre]

Maintainer Ulrich Riegel <ulrich.riegel@gmx.de>

Repository CRAN

Date/Publication 2021-03-03 09:30:02 UTC

R topics documented:

dGenPareto	3
dPareto	4
dPiecewisePareto	4
Example1_AP	5

Example1_EL	6
Excess_Frequency	6
Excess_Frequency.PGP_Model	7
Excess_Frequency.PPP_Model	7
Fit_PML_Curve	8
Fit_References	9
GenPareto_Layer_Mean	12
GenPareto_Layer_SM	13
GenPareto_Layer_Var	14
GenPareto_ML_Estimator_Alpha	15
is.PGP_Model	16
is.PPP_Model	17
is.valid.PGP_Model	18
is.valid.PPP_Model	18
Layer_Mean	19
Layer_Mean.PGP_Model	20
Layer_Mean.PPP_Model	20
Layer_Sd	21
Layer_Sd.PGP_Model	22
Layer_Sd.PPP_Model	23
Layer_Var	23
Layer_Var.PGP_Model	24
Layer_Var.PPP_Model	25
Local_Pareto_Alpha	26
Pareto_CDF	27
Pareto_Extrapolation	27
Pareto_Find_Alpha_btw_FQs	29
Pareto_Find_Alpha_btw_FQ_Layer	30
Pareto_Find_Alpha_btw_Layers	31
Pareto_Layer_Mean	32
Pareto_Layer_SM	33
Pareto_Layer_Var	33
Pareto_ML_Estimator_Alpha	34
Pareto_PDF	36
pGenPareto	36
PGP_Model	37
PiecewisePareto_CDF	38
PiecewisePareto_Layer_Mean	39
PiecewisePareto_Layer_SM	40
PiecewisePareto_Layer_Var	41
PiecewisePareto_Match_Layer_Losses	42
PiecewisePareto_ML_Estimator_Alpha	45
PiecewisePareto_PDF	46
pPareto	47
pPiecewisePareto	48
PPP_Model	49
PPP_Model_Excess_Frequency	50
PPP_Model_Exp_Layer_Loss	50

PPP_Model_Layer_Sd	51
PPP_Model_Layer_Var	52
PPP_Model_Simulate	52
print.PGP_Model	53
print.PPP_Model	53
qGenPareto	54
qPareto	54
qPiecewisePareto	55
rGenPareto	56
rPareto	57
rPiecewisePareto	57
Simulate_Losses	58
Simulate_Losses.PGP_Model	59
Simulate_Losses.PPP_Model	60

Index 61

dGenPareto	<i>Density of the generalized Pareto Distribution</i>
------------	---

Description

Calculates the density function of the generalized Pareto distribution

Usage

```
dGenPareto(x, t, alpha_ini, alpha_tail, truncation = NULL)
```

Arguments

x	Numeric. The function evaluates the density at x.
t	Numeric. Threshold of the Pareto distribution.
alpha_ini	Numeric. Initial Pareto alpha.
alpha_tail	Numeric. Tail Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the generalized Pareto distribution is truncated at truncation.

Value

Density function of the Pareto distribution with parameters t, alpha_ini and alpha_tail evaluated at x

Examples

```
x <- 0:10 * 1000
dGenPareto(x, 1000, 1, 3)
dGenPareto(x, 1000, 1, 3, truncation = 5000)
```

dPareto *Density of the Pareto Distribution*

Description

Calculates the density function of the Pareto distribution

Usage

```
dPareto(x, t, alpha, truncation = NULL)
```

Arguments

x	Numeric. The function evaluates the density at x.
t	Numeric. Threshold of the Pareto distribution.
alpha	Numeric. Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

Density function of the Pareto distribution with parameters t and alpha evaluated at x

Examples

```
x <- 0:10 * 1000
dPareto(x, 1000, 2)
dPareto(x, 1000, 2, truncation = 5000)
```

dPiecewisePareto *Density of the Piecewise Pareto Distribution*

Description

Calculates the density function of the piecewise Pareto distribution

Usage

```
dPiecewisePareto(x, t, alpha, truncation = NULL, truncation_type = "lp")
```

Arguments

x	Numeric. The function evaluates the density at x.
t	Numeric vector. Thresholds of the piecewise Pareto distribution.
alpha	Numeric vector. alpha[i] is the Pareto alpha in excess of t[i].
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.
truncation_type	Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.

Value

Density function of the piecewise Pareto distribution with parameter vectors t and alpha evaluated at x

Examples

```
t <- c(1000, 2000, 3000)
alpha <- c(1, 1.5, 2)
x <- 0:10 * 1000
dPiecewisePareto(x, t, alpha)
dPiecewisePareto(x, t, alpha, truncation = 5000, truncation_type = "lp")
dPiecewisePareto(x, t, alpha, truncation = 5000, truncation_type = "wd")
```

Example1_AP

Example data: Attachment Points

Description

Example data: Attachment Points

Usage

```
Example1_AP
```

Format

An object of class numeric of length 5.

 Example1_EL

Example data: Expected Losses

Description

Example data: Expected Losses

Usage

Example1_EL

Format

An object of class `numeric` of length 5.

Excess_Frequency

Expected Frequency in Excess of a Threshold

Description

Calculates the expected frequency in excess of a threshold for a collective model

Usage

```
Excess_Frequency(CollectiveModel, x = 0)
```

Arguments

`CollectiveModel`

A collective model object. Currently only `PPP_Models` are handled.

`x`

Numeric. Threshold.

Value

The expected frequency in excess of `x` for the given `CollectiveModel`

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Excess_Frequency(PPPM, c(-Inf, 0, 1000, 2000, 3000, Inf))
```

`Excess_Frequency.PGP_Model`*Expected Frequency in Excess of a Threshold*

Description

Calculates the expected frequency in excess of a threshold for a PGP_model

Usage

```
## S3 method for class 'PGP_Model'  
Excess_Frequency(CollectiveModel, x = 0)
```

Arguments

CollectiveModel	PGP_Model object.
x	Numeric. Threshold.

Value

The expected frequency in excess of x for the given CollectiveModel

Examples

```
PGPM <- PGP_Model(2, 1000, 1, 2, dispersion = 2)  
PGPM  
Excess_Frequency(PGPM, c(-Inf, 0, 1000, 2000, 3000, Inf))
```

`Excess_Frequency.PPP_Model`*Expected Frequency in Excess of a Threshold*

Description

Calculates the expected frequency in excess of a threshold for a PPP_model

Usage

```
## S3 method for class 'PPP_Model'  
Excess_Frequency(CollectiveModel, x = 0)
```

Arguments

CollectiveModel
 PPP_Model object.
 x
 Numeric. Threshold.

Value

The expected frequency in excess of x for the given CollectiveModel

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Excess_Frequency(PPPM, c(-Inf, 0, 1000, 2000, 3000, Inf))
```

 Fit_PML_Curve

Fits a Collective Model to a PML Curve

Description

Fits a PPP_Model that matches the values of a PML curve

Usage

```
Fit_PML_Curve(
  return_periods,
  amounts,
  tail_alpha = 2,
  truncation = NULL,
  truncation_type = "lp",
  dispersion = 1
)
```

Arguments

return_periods Numeric vector. Vector containing the return periods of the PML curve.
 amounts Numeric vector. Vector containing the loss amounts corresponding to the return periods.
 tail_alpha Numerical. Pareto alpha that is used above the highest amount of the PML curve.
 truncation Numeric. If truncation is not NULL and truncation > max(t), then the distribution is truncated at truncation.
 truncation_type Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.
 dispersion Numerical. Dispersion of the claim count distribution in the resulting PPP_Model.

Value

A PPP_Model object that contains the information about a collective model with a Panjer distributed claim count and a Piecewise Pareto distributed severity. The object contains the following elements:

- FQ Numerical. Frequency in excess of the lowest threshold of the piecewise Pareto distribution
- t Numeric vector. Vector containing the thresholds for the piecewise Pareto distribution
- alpha Numeric vector. Vector containing the Pareto alphas of the piecewise Pareto distribution
- truncation Numerical. If truncation is not NULL and $\text{truncation} > \max(t)$, then the distribution is truncated at truncation.
- truncation_type Character. If `truncation_type = "wd"` then the whole distribution is truncated. If `truncation_type = "lp"` then a truncated Pareto is used for the last piece.
- dispersion Numerical. Dispersion of the Panjer distribution (i.e. variance to mean ratio).
- Status Numerical indicator: 0 = success, 1 = some information has been ignored, 2 = no solution found
- Comment Character. Information on whether the fit was successful

Examples

```
return_periods <- c(1, 5, 10, 20, 50, 100)
amounts <- c(1000, 4000, 7000, 10000, 13000, 14000)

fit <- Fit_PML_Curve(return_periods, amounts)
1 / Excess_Frequency(fit, amounts)

fit <- Fit_PML_Curve(return_periods, amounts, tail_alpha = 1.5,
                    truncation = 20000, truncation_type = "wd")
1 / Excess_Frequency(fit, amounts)
```

Description

The function fits a collective model to a wishlist of references (expected layer losses and excess frequencies). The function allows to specify the family of the severity distribution that is used. Depending on this distribution family the function works slightly differently:

- For the severity distribution PiecewisePareto the function returns a PPP_Model that satisfies all the references
- For the severity distribution Pareto the function returns a PPP_Model that minimizes the squared relative deviations from the references
- For the severity distribution GenPareto the function returns a PGP_Model that minimizes the squared relative deviations from the references

Usage

```
Fit_References(
  Covers = NULL,
  Attachment_Points = NULL,
  Expected_Layer_Losses = NULL,
  Thresholds = NULL,
  Frequencies = NULL,
  model_threshold = min(c(Attachment_Points, Thresholds)),
  default_alpha = 2,
  dispersion = 1,
  alpha_max = 100,
  severity_distribution = "PiecewisePareto",
  ignore_inconsistent_references = FALSE
)
```

Arguments

Covers	Numeric vector. Vector containing the covers of the layers from the wishlist.
Attachment_Points	Numeric vector. Vector containing the attachment points of the layers from the wishlist.
Expected_Layer_Losses	Numeric vector. Vector containing the expected losses of the layers from the wishlist.
Thresholds	Numeric vector. Contains the thresholds from the wishlist for which excess frequencies are given.
Frequencies	Numeric vector. Expected frequencies excess the Thresholds from the wishlist.
model_threshold	Numerical. Lowest threshold of the fitted piecewise Pareto distribution.
default_alpha	Numerical. Default alpha for situations where an alpha has to be selected.
dispersion	Numerical. Dispersion of the claim count distribution in the resulting PPP_Model.
alpha_max	Numerical. Maximum alpha to be used for the matching.
severity_distribution	Character. Implemented distributions: "PiecewisePareto" (default), "Pareto" and "GenPareto".
ignore_inconsistent_references	Logical. If TRUE then inconsistent references are ignored in case of the piecewise Pareto distribution and the other references are used to fit the model

Value

For severity_distribution = "PiecewisePareto" or "Pareto": A PPP_Model object that contains the information about a collective model with a Panjer distributed claim count and a Piecewise Pareto distributed severity. The object contains the following elements:

- FQ Numerical. Frequency in excess of the lowest threshold of the piecewise Pareto distribution

- `t` Numeric vector. Vector containing the thresholds for the piecewise Pareto distribution
- `alpha` Numeric vector. Vector containing the Pareto alphas of the piecewise Pareto distribution
- `truncation` Numerical. If `truncation` is not NULL and `truncation > max(t)`, then the distribution is truncated at `truncation`.
- `truncation_type` Character. If `truncation_type = "wd"` then the whole distribution is truncated. If `truncation_type = "lp"` then a truncated Pareto is used for the last piece.
- `dispersion` Numerical. Dispersion of the Panjer distribution (i.e. variance to mean ratio).
- `Status` Numerical indicator: 0 = success, 1 = some information has been ignored, 2 = no solution found
- `Comment` Character. Information on whether the fit was successful

For `severity_distribution = "GenPareto"`: A `PGP_Model` object that contains the information about a collective model with a Panjer distributed claim count and a Piecewise Pareto distributed severity. The object contains the following elements:

- `FQ` Expected claim count of the collective model.
- `t` Numeric. Threshold of the Pareto distribution.
- `alpha_ini` Numeric. Initial Pareto alpha (at `t`).
- `alpha_tail` Numeric. Tail Pareto alpha.
- `truncation` If `truncation` is not NULL and `truncation > t`, then the Pareto distribution is truncated at `truncation`.
- `dispersion` Numerical. Dispersion of the Panjer distribution (i.e. variance to mean ratio).
- `Status` Numerical indicator: 0 = success, 1 = some information has been ignored, 2 = no solution found
- `Comment` Character. Information on whether the fit was successful

Examples

```
covers <- c(1000, 1000, 1000)
att_points <- c(1000, 2000, 5000)
exp_losses <- c(100, 50, 10)
thresholds <- c(4000, 10000)
fqs <- c(0.04, 0.005)
fit <- Fit_References(covers, att_points, exp_losses, thresholds, fqs)
Layer_Mean(fit, covers, att_points)
Excess_Frequency(fit, thresholds)
fit <- Fit_References(covers, att_points, exp_losses, thresholds, fqs,
                    severity_distribution = "Pareto")
Layer_Mean(fit, covers, att_points)
Excess_Frequency(fit, thresholds)
fit <- Fit_References(covers, att_points, exp_losses,
                    severity_distribution = "GenPareto")
Layer_Mean(fit, covers, att_points)
```

GenPareto_Layer_Mean *Layer Mean of the generalized Pareto Distribution*

Description

Calculates the expected loss of a generalized Pareto distribution in a reinsurance layer

Usage

```
GenPareto_Layer_Mean(
  Cover,
  AttachmentPoint,
  t,
  alpha_ini,
  alpha_tail,
  truncation = NULL
)
```

Arguments

Cover	Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.
t	Numeric. Threshold of the Pareto distribution. If t is NULL (default) then t <- Attachment Point is used.
alpha_ini	Numeric. Initial Pareto alpha (at t).
alpha_tail	Numeric. Tail Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

The expected loss of the (truncated) Pareto distribution with parameters t and alpha in the layer Cover xs AttachmentPoint

Examples

```
GenPareto_Layer_Mean(4000, 1000, 1000, 1, 3)
GenPareto_Layer_Mean(4000, 1000, t = 1000, alpha_ini = 1, alpha_tail = 3)
GenPareto_Layer_Mean(4000, 1000, t = 5000, alpha_ini = 1, alpha_tail = 3)
GenPareto_Layer_Mean(4000, 1000, t = 1000, alpha_ini = 1, alpha_tail = 3, truncation = 5000)
GenPareto_Layer_Mean(9000, 1000, t = 1000, alpha_ini = 1, alpha_tail = 3, truncation = 5000)
```

GenPareto_Layer_SM *Second Layer Moment of the Generalized Pareto Distribution*

Description

Calculates the second moment of a generalized Pareto distribution in a reinsurance layer

Usage

```
GenPareto_Layer_SM(
  Cover,
  AttachmentPoint,
  t,
  alpha_ini,
  alpha_tail,
  truncation = NULL
)
```

Arguments

Cover	Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.
t	Numeric. Threshold of the Pareto distribution. If t is NULL (default) then t <- Attachment Point is used
alpha_ini	Numeric. Initial Pareto alpha (at t).
alpha_tail	Numeric. Tail Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

The second moment of the (truncated) generalized Pareto distribution with parameters t, alpha_ini and alpha_tail in the layer Cover xs AttachmentPoint

Examples

```
GenPareto_Layer_SM(4000, 1000, 1000, 1, 2)
GenPareto_Layer_SM(4000, 1000, t = 1000, alpha_ini = 1, alpha_tail = 3)
GenPareto_Layer_SM(4000, 1000, t = 5000, alpha_ini = 1, alpha_tail = 3)
GenPareto_Layer_SM(4000, 1000, t = 1000, alpha_ini = 1, alpha_tail = 3, truncation = 5000)
GenPareto_Layer_SM(9000, 1000, t = 1000, alpha_ini = 1, alpha_tail = 3, truncation = 5000)
```

GenPareto_Layer_Var *Layer Variance of the Generalized Pareto Distribution*

Description

Calculates the variance of a generalized Pareto distribution in a reinsurance layer

Usage

```
GenPareto_Layer_Var(
  Cover,
  AttachmentPoint,
  t,
  alpha_ini,
  alpha_tail,
  truncation = NULL
)
```

Arguments

Cover	Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.
t	Numeric. Threshold of the Pareto distribution. If t is NULL (default) then t <- Attachment Point is used
alpha_ini	Numeric. Initial Pareto alpha (at t).
alpha_tail	Numeric. Tail Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

Variance of the (truncated) generalized Pareto distribution with parameters t, alpha_ini and alpha_tail in the layer Cover xs AttachmentPoint

Examples

```
GenPareto_Layer_Var(4000, 1000, 1000, 1, 2)
GenPareto_Layer_Var(4000, 1000, t = 1000, alpha_ini = 1, alpha_tail = 3)
GenPareto_Layer_Var(4000, 1000, t = 5000, alpha_ini = 1, alpha_tail = 3)
GenPareto_Layer_Var(4000, 1000, t = 1000, alpha_ini = 1, alpha_tail = 3, truncation = 5000)
GenPareto_Layer_Var(9000, 1000, t = 1000, alpha_ini = 1, alpha_tail = 3, truncation = 5000)
```

 GenPareto_ML_Estimator_Alpha

Maximum Likelihood Estimation of the Pareto Alphas of a Generalized Pareto Distribution

Description

Calculates the maximum likelihood estimators of the parameters `alpha_ini` and `alpha_tail` of a generalized Pareto distribution with known threshold and (if applicable) known truncation

Usage

```
GenPareto_ML_Estimator_Alpha(
  losses,
  t,
  truncation = NULL,
  reporting_thresholds = NULL,
  is.censored = NULL,
  weights = NULL,
  alpha_min = 0.001,
  alpha_max = 10
)
```

Arguments

<code>losses</code>	Numeric vector. Losses that are used for the ML estimation.
<code>t</code>	Numeric or numeric vector. Threshold of the generalized Pareto distribution. Alternatively, <code>t</code> can be a vector of same length as <code>losses</code> . In this case <code>t[i]</code> is the reporting threshold of <code>losses[i]</code> .
<code>truncation</code>	Numeric. If <code>truncation</code> is not <code>NULL</code> and <code>truncation > t</code> , then the generalized Pareto distribution is truncated at <code>truncation</code> .
<code>reporting_thresholds</code>	Numeric vector. Allows to enter loss specific reporting thresholds. If <code>NULL</code> then all reporting thresholds are assumed to be less than or equal to <code>t</code> .
<code>is.censored</code>	Logical vector. <code>TRUE</code> indicates that a loss has been censored by the policy limit. The assumption is that the uncensored losses are Generalized Pareto distributed with the alphas we are looking for. <code>is.censored = NULL</code> means that no losses are censored.
<code>weights</code>	Numeric vector. Weights for the losses. For instance <code>weights[i] = 2</code> and <code>weights[j] = 1</code> for <code>j != i</code> has the same effect as adding another loss of size <code>loss[i]</code> .
<code>alpha_min</code>	Numeric. Lower bound for the estimated alphas.
<code>alpha_max</code>	Numeric. Upper bound for the estimated alphas.

Value

Maximum likelihood estimator for the parameters `alpha_ini` and `alpha_tail` of a generalized Pareto distribution with threshold `t` given the observations `losses`

Examples

```
losses <- rGenPareto(1000, 1000, 2,3)
GenPareto_ML_Estimator_Alpha(losses, 1000)
losses <- rGenPareto(1000, 1000, 2, 1, truncation = 10000)
GenPareto_ML_Estimator_Alpha(losses, 1000)
GenPareto_ML_Estimator_Alpha(losses, 1000, truncation = 10000)

t <- 1000
alpha_ini <- 1
alpha_tail <- 3
losses <- rGenPareto(5000, t, alpha_ini, alpha_tail)
reporting_thresholds <- rPareto(5000, 1000, 3)
reported <- losses > reporting_thresholds
losses <- losses[reported]
reporting_thresholds <- reporting_thresholds[reported]
GenPareto_ML_Estimator_Alpha(losses, t)
GenPareto_ML_Estimator_Alpha(losses, t, reporting_thresholds = reporting_thresholds)
limit <- 3000
censored <- losses > limit
losses[censored] <- limit
reported <- losses > reporting_thresholds
losses <- losses[reported]
censored <- censored[reported]
reporting_thresholds <- reporting_thresholds[reported]
GenPareto_ML_Estimator_Alpha(losses, t, reporting_thresholds = reporting_thresholds)
GenPareto_ML_Estimator_Alpha(losses, t, reporting_thresholds = reporting_thresholds,
                             is.censored = censored)

losses <- c(190, 600, 120, 270, 180, 120)
w <- rep(1, length(losses))
w[1] <- 3
losses2 <- c(losses, losses[1], losses[1])
GenPareto_ML_Estimator_Alpha(losses, 100, weights = w)
GenPareto_ML_Estimator_Alpha(losses2, 100)
```

is.PGP_Model

Check if an object is a PGP_Model

Description

Checks if the class of an object is 'PGP_Model'

Usage

```
is.PGP_Model(x)
```


Arguments

x Object to be checked.

Examples

```
PGPM <- PGP_Model(2, 1000, 1, 2, dispersion = 2)
PGPM
is.valid.PGP_Model(PGPM)
is.valid.PGP_Model(PGPM, comment = TRUE)

PGPM$alpha_tail <- -2
is.PGP_Model(PGPM)
is.valid.PGP_Model(PGPM)
is.valid.PGP_Model(PGPM, comment = TRUE)
```

is.PPP_Model *Check if an object is a PPP_Model*

Description

Checks if the class of an object is 'PPP_Model'

Usage

```
is.PPP_Model(x)
```

Arguments

x Object to be checked.

Examples

```
PPPM <- PPP_Model(2, c(1000,2000), c(1,2), dispersion = 2)
PPPM
is.valid.PPP_Model(PPPM)

PPPM$alpha <- 2
is.valid.PPP_Model(PPPM)
is.PPP_Model(PPPM)
```

```
is.valid.PGP_Model      Check if an object is a valid PGP_Model
```

Description

Checks if an object is a PGP_Model object and whether it is valid for the use in functions like Layer_Mean

Usage

```
is.valid.PGP_Model(x, comment = FALSE)
```

Arguments

x	Object to be checked.
comment	If FALSE then the function returns a boolean indicating whether x is a valid PGP_Model. If TRUE then the function returns a comment instead.

Examples

```
PGPM <- PGP_Model(2, 1000, 1, 2, dispersion = 2)
PGPM
is.valid.PGP_Model(PGPM)
is.valid.PGP_Model(PGPM, comment = TRUE)

PGPM$alpha_tail <- -2
is.valid.PGP_Model(PGPM)
is.valid.PGP_Model(PGPM, comment = TRUE)
```

```
is.valid.PPP_Model      Check if an object is a valid PPP_Model
```

Description

Checks if an object is a PPP_Model object and whether it is valid for the use in functions like Layer_Mean

Usage

```
is.valid.PPP_Model(x, comment = FALSE)
```

Arguments

x	Object to be checked.
comment	If FALSE then the function returns a boolean indicating whether x is a valid PPP_Model. If TRUE then the function returns a comment instead.

Examples

```

PPPM <- PPP_Model(2, c(1000,2000), c(1,2), dispersion = 2)
PPPM
is.valid.PPP_Model(PPPM)
is.valid.PPP_Model(PPPM, comment = TRUE)

PPPM$alpha <- 2
is.valid.PPP_Model(PPPM)
is.valid.PPP_Model(PPPM, comment = TRUE)

```

Layer_Mean

Expected Loss of a Reinsurance Layer

Description

Calculates the expected loss of a reinsurance layer for a collective model

Usage

```
Layer_Mean(CollectiveModel, Cover = Inf, AttachmentPoint = 0)
```

Arguments

CollectiveModel	A collective model object. Currently only PPP_Models are handled.
Cover	Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.

Value

The expected loss of the layer Cover xs AttachmentPoint for the given CollectiveModel

Examples

```

PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Example1_AP
Example1_Cov
Example1_EL
Layer_Mean(PPPM, Example1_Cov, Example1_AP)

```

Layer_Mean.PGP_Model *Expected Loss of a Reinsurance Layer*

Description

Calculates the expected loss of a reinsurance layer for a PGP_Model

Usage

```
## S3 method for class 'PGP_Model'
Layer_Mean(CollectiveModel, Cover = Inf, AttachmentPoint = 0)
```

Arguments

CollectiveModel
PGP_Model object.

Cover
Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.

AttachmentPoint
Numeric. Attachment point of the reinsurance layer.

Value

The expected loss of the layer Cover xs AttachmentPoint for the given CollectiveModel

Examples

```
PGPM <- PGP_Model(2, 1000, 1, 2, dispersion = 2)
PGPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Example1_AP
Example1_Cov
Example1_EL
Layer_Mean(PGPM, Example1_Cov, Example1_AP)
```

Layer_Mean.PPP_Model *Expected Loss of a Reinsurance Layer*

Description

Calculates the expected loss of a reinsurance layer for a PPP_Model

Usage

```
## S3 method for class 'PPP_Model'
Layer_Mean(CollectiveModel, Cover = Inf, AttachmentPoint = 0)
```

Arguments

CollectiveModel
 PPP_Model object.

Cover
 Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.

AttachmentPoint
 Numeric. Attachment point of the reinsurance layer.

Value

The expected loss of the layer Cover xs AttachmentPoint for the given CollectiveModel

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Example1_AP
Example1_Cov
Example1_EL
Layer_Mean(PPPM, Example1_Cov, Example1_AP)
```

 Layer_Sd

Standard Deviation of a Reinsurance Layer

Description

Calculates the standard deviation of the loss in a reinsurance layer for a collective model

Usage

```
Layer_Sd(CollectiveModel, Cover = Inf, AttachmentPoint = 0)
```

Arguments

CollectiveModel
 A collective model object. Currently only PPP_Models are handled.

Cover
 Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.

AttachmentPoint
 Numeric. Attachment point of the reinsurance layer.

Value

The standard deviation of the loss in the layer Cover xs AttachmentPoint for the given CollectiveModel

Examples

```

PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Layer_Sd(PPPM, Example1_Cov, Example1_AP)

```

Layer_Sd.PGP_Model *Standard Deviation of a Reinsurance Layer*

Description

Calculates the standard deviation of the loss in a reinsurance layer for a PGP_model

Usage

```

## S3 method for class 'PGP_Model'
Layer_Sd(CollectiveModel, Cover = Inf, AttachmentPoint = 0)

```

Arguments

CollectiveModel PGP_Model object.

Cover Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.

AttachmentPoint Numeric. Attachment point of the reinsurance layer.

Value

The standard deviation of the loss in the layer Cover xs AttachmentPoint for the given CollectiveModel

Examples

```

PGPM <- PGP_Model(2, 1000, 1, 2, dispersion = 2)
PGPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Layer_Sd(PGPM, Example1_Cov, Example1_AP)

```

Layer_Sd.PPP_Model *Standard Deviation of a Reinsurance Layer*

Description

Calculates the standard deviation of the loss in a reinsurance layer for a PPP_model

Usage

```
## S3 method for class 'PPP_Model'
Layer_Sd(CollectiveModel, Cover = Inf, AttachmentPoint = 0)
```

Arguments

CollectiveModel PPP_Model object.

Cover Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.

AttachmentPoint Numeric. Attachment point of the reinsurance layer.

Value

The standard deviation of the loss in the layer Cover xs AttachmentPoint for the given CollectiveModel

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Layer_Sd(PPPM, Example1_Cov, Example1_AP)
```

Layer_Var *Variance of a Reinsurance Layer*

Description

Calculates the variance of the loss in a reinsurance layer for a collective model

Usage

```
Layer_Var(CollectiveModel, Cover = Inf, AttachmentPoint = 0)
```

Arguments

CollectiveModel
 A collective model object. Currently only PPP_Models are handled.

Cover
 Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.

AttachmentPoint
 Numeric. Attachment point of the reinsurance layer.

Value

The variance of the loss in the layer Cover xs AttachmentPoint for the given CollectiveModel

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Layer_Var(PPPM, Example1_Cov, Example1_AP)
```

Layer_Var.PGP_Model1 *Variance of a Reinsurance Layer*

Description

Calculates the variance of the loss in a reinsurance layer for a PGP_model

Usage

```
## S3 method for class 'PGP_Model'
Layer_Var(CollectiveModel, Cover = Inf, AttachmentPoint = 0)
```

Arguments

CollectiveModel
 PGP_Model object.

Cover
 Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.

AttachmentPoint
 Numeric. Attachment point of the reinsurance layer.

Value

The variance of the loss in the layer Cover xs AttachmentPoint for the given CollectiveModel

Examples

```
PGPM <- PGP_Model(2, 1000, 1, 2, dispersion = 2)
PGPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Layer_Var(PGPM, Example1_Cov, Example1_AP)
```

Layer_Var.PPP_Model *Variance of a Reinsurance Layer*

Description

Calculates the variance of the loss in a reinsurance layer for a PPP_model

Usage

```
## S3 method for class 'PPP_Model'
Layer_Var(CollectiveModel, Cover = Inf, AttachmentPoint = 0)
```

Arguments

CollectiveModel PPP_Model object.

Cover Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.

AttachmentPoint Numeric. Attachment point of the reinsurance layer.

Value

The variance of the loss in the layer Cover xs AttachmentPoint for the given CollectiveModel

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Layer_Var(PPPM, Example1_Cov, Example1_AP)
```

Local_Pareto_Alpha *Local Pareto Alpha*

Description

Calculates the local Pareto alpha of the normal, lognormal and gamma distribution

Usage

```
Local_Pareto_Alpha(x, distribution, ...)
```

Arguments

x	Numeric. Vector of thresholds at which the local Pareto alpha is calculated.
distribution	Character. <ul style="list-style-type: none"> • 'lnorm' for lognormal distribution (arguments: meanlog, sdlog) • 'norm' for normal distribution (arguments: mean, sd) • 'gamma' for gamma distribution (arguments: shape, rate, scale) • 'weibull' for weibull distribution (arguments: shape, scale) • 'exp' for exponential distribution (arguments: rate) • 'Pareto' for Pareto distribution (arguments: t, alpha, truncation = NULL) • 'GenPareto' for exp distribution (arguments: t, alpha_ini, alpha_tail, truncation = NULL) • 'PiecewisePareto' for exp distribution (arguments: t, alpha, truncation = NULL, truncation_type = 'lp')
...	Arguments for the selected distribution

Value

Local Pareto alpha of the selected distribution at x

References

Riegel, U. (2008) Generalizations of common ILF models. *Blaetter der DGVMF* 29: 45–71

Examples

```
x <- 1:10 * 1e6
Local_Pareto_Alpha(x, "norm", mean = 5e6, sd = 2e6)
Local_Pareto_Alpha(x, "lnorm", meanlog = 0, sdlog = 4)
Local_Pareto_Alpha(x, "gamma", shape = 5, rate = 1e-6)
Local_Pareto_Alpha(x, "weibull", shape = 0.5, scale = 1e6)
Local_Pareto_Alpha(x, "exp", rate = 1e-6)
Local_Pareto_Alpha(x, "Pareto", t = 1e6, alpha = 1, truncation = 20e6)
Local_Pareto_Alpha(x, "GenPareto", t = 1e6, alpha_ini = 1, alpha_tail = 2)
Local_Pareto_Alpha(x, "PiecewisePareto", t = c(1e6, 3e6, 5e6), alpha = c(1, 2, 3),
truncation = 20e6, truncation_type = "wd")
```

Pareto_CDF	<i>Distribution Function of the Pareto Distribution</i>
------------	---

Description

Calculates the cumulative distribution function of a Pareto distribution. This function is deprecated. Use `pPareto` instead.

Usage

```
Pareto_CDF(x, t, alpha, truncation = NULL)
```

Arguments

<code>x</code>	Numeric. The function evaluates the CDF at <code>x</code> .
<code>t</code>	Numeric. Threshold of the Pareto distribution.
<code>alpha</code>	Numeric. Pareto alpha.
<code>truncation</code>	Numeric. If <code>truncation</code> is not <code>NULL</code> and <code>truncation > t</code> , then the Pareto distribution is truncated at <code>truncation</code> .

Value

Distribution function of the Pareto distribution with parameters `t` and `alpha` evaluated at `x`

Examples

```
x <- 0:10 * 1000
pPareto(x, 1000, 2)
pPareto(x, 1000, 2, truncation = 5000)
```

Pareto_Extrapolation	<i>Pareto Extrapolation</i>
----------------------	-----------------------------

Description

Uses a Pareto distribution to derive the expected loss of a layer from the expected loss of another layer

Usage

```
Pareto_Extrapolation(
  Cover_1,
  AttachmentPoint_1,
  Cover_2,
  AttachmentPoint_2,
  alpha,
  ExpLoss_1 = NULL,
  truncation = NULL
)
```

Arguments

Cover_1	Numeric. Cover of the layer from which we extrapolate. Use Inf for unlimited layers.
AttachmentPoint_1	Numeric. Attachment point of the layer from which we extrapolate.
Cover_2	Numeric. Cover of the layer to which we extrapolate. Use Inf for unlimited layers.
AttachmentPoint_2	Numeric. Attachment point of the layer to which we extrapolate.
alpha	Numeric. Pareto alpha used for the extrapolation.
ExpLoss_1	Numeric. Expected loss of the layer from which we extrapolate. If NULL (default) then the function provides only the ratio between the expected losses of the layers.
truncation	Numeric. If truncation is not NULL and $\text{truncation} > \text{AttachmentPoint}_1$, then the Pareto distribution is truncated at truncation.

Value

The expected loss of the layer Cover_2 xs AttachmentPoint_2 given that Cover_1 xs AttachmentPoint_1 has expected loss ExpLoss_1 and assuming a (truncated) Pareto distribution with parameters t and α . If missing then $\text{ExpLoss}_1 == 1$ is assumed.

References

Riegel, U. (2018) Matching tower information with piecewise Pareto. European Actuarial Journal 8(2): 437–460

Examples

```
Pareto_Extrapolation(1000, 1000, 2000, 2000, 2, ExpLoss_1 = 100)
Pareto_Extrapolation(1000, 1000, 2000, 2000, 2) * 100
Pareto_Extrapolation(1000, 1000, 2000, 2000, 2, truncation = 5000, ExpLoss_1 = 100)
Pareto_Extrapolation(1000, 1000, 2000, 2000, 2, truncation = 5000) * 100
```

Pareto_Find_Alpha_bt看_FQs

Pareto Alpha Between Two Frequencies

Description

Finds the Pareto alpha between two excess frequencies

Usage

```
Pareto_Find_Alpha_bt看_FQs(  
  Threshold_1,  
  Frequency_1,  
  Threshold_2,  
  Frequency_2,  
  max_alpha = 100,  
  tolerance = 1e-10,  
  truncation = NULL  
)
```

Arguments

Threshold_1	Numeric. Threshold 1
Frequency_1	Numeric. Expected frequency in excess of Threshold_1
Threshold_2	Numeric. Threshold 2
Frequency_2	Numeric. Expected frequency in excess of Threshold_2
max_alpha	Numeric. Upper limit for the alpha that is returned.
tolerance	Numeric. Accuracy of the result.
truncation	Numeric. If truncation is not NULL then the Pareto distribution is truncated at truncation.

Value

The Pareto alpha between the expected number of claims Frequency_1 excess Threshold_1 and the expected number of claims Frequency_2 excess Threshold_2

References

Riegel, U. (2018) Matching tower information with piecewise Pareto. *European Actuarial Journal* 8(2): 437–460

Examples

```
Pareto_Find_Alpha_bt看_FQs(1000, 1, 2000, 0.5)  
Pareto_Find_Alpha_bt看_FQs(1000, 1, 2000, 0.5, truncation = 5000)
```

 Pareto_Find_Alpha_bt看_FQ_Layer

Pareto Alpha Between a Frequency and a Layer

Description

Finds the Pareto alpha between an excess frequency and the expected loss of a layer

Usage

```
Pareto_Find_Alpha_bt看_FQ_Layer(
  Threshold,
  Frequency,
  Cover,
  AttachmentPoint,
  ExpLoss,
  max_alpha = 100,
  tolerance = 1e-10,
  truncation = NULL
)
```

Arguments

Threshold	Numeric. Threshold
Frequency	Numeric. Expected frequency in excess of Thershold
Cover	Numeric. Cover of the second layer.
AttachmentPoint	Numeric. Attachment point of the layer.
ExpLoss	Numeric. Expected loss of the layer.
max_alpha	Numeric. Upper limit for the alpha that is returned.
tolerance	Numeric. Accuracy of the result.
truncation	Numeric. If truncation is not NULL then the Pareto distribution is truncated at truncation.

Value

The Pareto alpha between the expected number of claims Frequency excess Threshold and the layer Cover xs AttachmentPoint with expected loss ExpLoss

References

Riegel, U. (2018) Matching tower information with piecewise Pareto. European Actuarial Journal 8(2): 437–460

Examples

```
Pareto_Find_Alpha_bt看_FQ_Layer(1000, 1, 1000, 1000, 500)
Pareto_Find_Alpha_bt看_FQ_Layer(1000, 1, 1000, 1000, 500, truncation = 5000)
```

Pareto_Find_Alpha_bt看_Layers

Pareto Alpha Between Two Layers

Description

Finds the Pareto alpha between two layers

Usage

```
Pareto_Find_Alpha_bt看_Layers(
  Cover_1,
  AttachmentPoint_1,
  ExpLoss_1,
  Cover_2,
  AttachmentPoint_2,
  ExpLoss_2,
  max_alpha = 100,
  tolerance = 1e-10,
  truncation = NULL
)
```

Arguments

Cover_1	Numeric. Cover of the first layer.
AttachmentPoint_1	Numeric. Attachment point of the first layer.
ExpLoss_1	Numeric. Expected loss of the first layer.
Cover_2	Numeric. Cover of the second layer.
AttachmentPoint_2	Numeric. Attachment point of the second layer.
ExpLoss_2	Numeric. Expected loss of the second layer.
max_alpha	Numeric. Upper limit for the alpha that is returned.
tolerance	Numeric. Accuracy of the result.
truncation	Numeric. If truncation is not NULL then the Pareto distribution is truncated at truncation.

Value

The Pareto alpha between the layer Cover_1 xs AttachmentPoint_1 with expected loss ExpLoss_1 and the layer Cover_2 xs AttachmentPoint_2 with expected loss ExpLoss_2

References

Riegel, U. (2018) Matching tower information with piecewise Pareto. *European Actuarial Journal* 8(2): 437–460

Examples

```
Pareto_Find_Alpha_bt看_Layers(100, 100, 100, 200, 200, 50)
Pareto_Find_Alpha_bt看_Layers(100, 100, 100, 200, 200, 50, truncation = 500)
```

Pareto_Layer_Mean	<i>Layer Mean of the Pareto Distribution</i>
-------------------	--

Description

Calculates the expected loss of a Pareto distribution in a reinsurance layer

Usage

```
Pareto_Layer_Mean(Cover, AttachmentPoint, alpha, t = NULL, truncation = NULL)
```

Arguments

Cover	Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.
alpha	Numeric. Pareto alpha.
t	Numeric. Threshold of the Pareto distribution. If t is NULL (default) then t <- Attachment Point is used.
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

The expected loss of the (truncated) Pareto distribution with parameters t and alpha in the layer Cover xs AttachmentPoint

Examples

```
Pareto_Layer_Mean(4000, 1000, 2)
Pareto_Layer_Mean(4000, 1000, alpha = 2, t = 1000)
Pareto_Layer_Mean(4000, 1000, alpha = 2, t = 5000)
Pareto_Layer_Mean(4000, 1000, alpha = 2, t = 1000, truncation = 5000)
Pareto_Layer_Mean(9000, 1000, alpha = 2, t = 1000, truncation = 5000)
```

Pareto_Layer_SM	<i>Second Layer Moment of the Pareto Distribution</i>
-----------------	---

Description

Calculates the second moment of a Pareto distribution in a reinsurance layer

Usage

```
Pareto_Layer_SM(Cover, AttachmentPoint, alpha, t = NULL, truncation = NULL)
```

Arguments

Cover	Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.
alpha	Numeric. Pareto alpha.
t	Numeric. Threshold of the Pareto distribution. If t is NULL (default) then t < Attachment Point is used
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

The second moment of the (truncated) Pareto distribution with parameters t and alpha in the layer Cover xs AttachmentPoint

Examples

```
Pareto_Layer_SM(4000, 1000, 2)
Pareto_Layer_SM(4000, 1000, alpha = 2, t = 1000)
Pareto_Layer_SM(4000, 1000, alpha = 2, t = 5000)
Pareto_Layer_SM(4000, 1000, alpha = 2, t = 1000, truncation = 5000)
Pareto_Layer_SM(9000, 1000, alpha = 2, t = 1000, truncation = 5000)
```

Pareto_Layer_Var	<i>Layer Variance of the Pareto Distribution</i>
------------------	--

Description

Calculates the variance of a Pareto distribution in a reinsurance layer

Usage

```
Pareto_Layer_Var(Cover, AttachmentPoint, alpha, t = NULL, truncation = NULL)
```

Arguments

Cover	Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.
alpha	Numeric. Pareto alpha.
t	Numeric. Threshold of the Pareto distribution. If t is NULL (default) then t <- Attachment Point is used.
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

The variance of the (truncated) Pareto distribution with parameters t and alpha in the layer Cover
xs AttachmentPoint

Examples

```
Pareto_Layer_Var(4000, 1000, 2)
Pareto_Layer_Var(4000, 1000, alpha = 2, t = 1000)
Pareto_Layer_Var(4000, 1000, alpha = 2, t = 5000)
Pareto_Layer_Var(4000, 1000, alpha = 2, t = 1000, truncation = 5000)
Pareto_Layer_Var(9000, 1000, alpha = 2, t = 1000, truncation = 5000)
```

Pareto_ML_Estimator_Alpha

Maximum Likelihood Estimation of the Alpha of a Pareto distribution

Description

Calculates the maximum likelihood estimator for the parameter alpha of a Pareto distribution with a known threshold and (if applicable) a known truncation

Usage

```
Pareto_ML_Estimator_Alpha(
  losses,
  t,
  truncation = NULL,
  reporting_thresholds = NULL,
  is.censored = NULL,
  weights = NULL,
  alpha_min = 0.001,
  alpha_max = 10
)
```

Arguments

losses	Numeric vector. Losses that are used for the ML estimation.
t	Numeric. Threshold of the Pareto distribution.
truncation	Numeric. If truncation is not NULL, then the Pareto distribution is truncated at truncation.
reporting_thresholds	Numeric vector. Allows to enter loss specific reporting thresholds. If NULL then all reporting thresholds are assumed to be less than or equal to t.
is.censored	Logical vector. TRUE indicates that a loss has been censored by the policy limit. The assumption is that the uncensored losses are Pareto distributed with the alpha we are looking for. is.censored = NULL means that no losses are censored.
weights	Numeric vector. Weights for the losses. For instance weights[i] = 2 and weights[j] = 1 for j != i has the same effect as adding another loss of size loss[i].
alpha_min	Numeric. Lower bound for alpha (only used in truncated case).
alpha_max	Numeric. Upper bound for alpha (only used in truncated case).

Value

Maximum likelihood estimator for the parameter alpha of a Pareto distribution with threshold t given the observations losses

Examples

```

losses <- rPareto(100, 1000, 2)
Pareto_ML_Estimator_Alpha(losses, 1000)
losses <- rPareto(100, 1000, 2, truncation = 2000)
Pareto_ML_Estimator_Alpha(losses, 1000)
Pareto_ML_Estimator_Alpha(losses, 1000, truncation = 2000)

t <- 100
alpha <- 2
losses <- rPareto(10000, t, alpha)
reporting_thresholds <- rPareto(10000, t, 5)
index <- losses > reporting_thresholds
losses <- losses[index]
reporting_thresholds <- reporting_thresholds[index]
Pareto_ML_Estimator_Alpha(losses, t)
Pareto_ML_Estimator_Alpha(losses, t, reporting_thresholds = reporting_thresholds)

losses <- rPareto(10, 1000, 2)
w <- rep(1, 10)
w[1] <- 3
losses2 <- c(losses, losses[1], losses[1])
Pareto_ML_Estimator_Alpha(losses, 1000, weights = w)
Pareto_ML_Estimator_Alpha(losses2, 1000)

```

Pareto_PDF *Density of the Pareto Distribution*

Description

Calculates the density function of the Pareto distribution. This function is deprecated. Use dPareto instead.

Usage

```
Pareto_PDF(x, t, alpha, truncation = NULL)
```

Arguments

x	Numeric. The function evaluates the density at x
t	Numeric. Threshold of the Pareto distribution.
alpha	Numeric. Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

Density function of the Pareto distribution with parameters t and alpha evaluated at x

Examples

```
x <- 0:10 * 1000
dPareto(x, 1000, 2)
dPareto(x, 1000, 2, truncation = 5000)
```

pGenPareto *Distribution Function of the generalized Pareto Distribution*

Description

Calculates the cumulative distribution function of a generalized Pareto distribution

Usage

```
pGenPareto(x, t, alpha_ini, alpha_tail, truncation = NULL)
```

Arguments

x	Numeric. The function evaluates the CDF at x.
t	Numeric. Threshold of the generalized Pareto distribution.
alpha_ini	Numeric. Initial Pareto alpha.
alpha_tail	Numeric. Tail Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the generalized Pareto distribution is truncated at truncation.

Value

Distribution function of the generalized Pareto distribution with parameters t, alpha_ini and alpha_tail evaluated at x

Examples

```
x <- 0:10 * 1000
pGenPareto(x, 1000, 1, 3)
pGenPareto(x, 1000, 1, 3, truncation = 5000)
```

PGP_Model

PGP_Model (Collective Panjer & Generalized Pareto Model) Object

Description

Constructor function for the PGP_Model object

Usage

```
PGP_Model(  
  FQ = NULL,  
  t = NULL,  
  alpha_ini = NULL,  
  alpha_tail = NULL,  
  truncation = NULL,  
  dispersion = 1,  
  Status = 0,  
  Comment = "OK"  
)
```

Arguments

FQ	Numerical. Expected claim count of the collective model.
t	Numeric. Threshold of the Pareto distribution. If t is NULL (default) then t <-Attachment Point is used
alpha_ini	Numeric. Initial Pareto alpha (at t).
alpha_tail	Numeric. Tail Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.
dispersion	Numerical. Dispersion of the Panjer distribution (i.e. variance to mean ratio).
Status	Numerical indicator if a function returns a PGP_Model object: 0 = success, 1 = some information has been ignored, 2 = no solution found
Comment	Charakter. An optional comment.

Examples

```
PGPM <- PGP_Model(2, t = 1000, alpha_ini = 1, alpha_tail = 2 , dispersion = 2)
PGPM
```

PiecewisePareto_CDF *Distribution Function of the Piecewise Pareto Distribution*

Description

Calculates the cumulative distribution function of a Piecewise Pareto Distribution. This function is deprecated. Use pPiecewisePareto instead.

Usage

```
PiecewisePareto_CDF(x, t, alpha, truncation = NULL, truncation_type = "lp")
```

Arguments

x	Numeric. The function evaluates the CDF at x.
t	Numeric vector. Thresholds of the piecewise Pareto distribution.
alpha	Numeric vector. alpha[i] is the Pareto alpha in excess of t[i].
truncation	Numeric. If truncation is not NULL and truncation > t, then the distribution is truncated at truncation.
truncation_type	Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.

Value

Distribution function of the piecewise Pareto distribution with parameter vectors t and α evaluated at x

References

Riegel, U. (2018) Matching tower information with piecewise Pareto. *European Actuarial Journal* 8(2): 437–460

Examples

```
t <- c(1000, 2000, 3000)
alpha <- c(1, 1.5, 2)
x <- 0:10 * 1000
pPiecewisePareto(x, t, alpha)
pPiecewisePareto(x, t, alpha, truncation = 5000, truncation_type = "lp")
pPiecewisePareto(x, t, alpha, truncation = 5000, truncation_type = "wd")
```

PiecewisePareto_Layer_Mean

Layer Mean of the Piecewise Pareto Distribution

Description

Calculates the expected loss of a piecewise Pareto distribution in a reinsurance layer

Usage

```
PiecewisePareto_Layer_Mean(
  Cover,
  AttachmentPoint,
  t,
  alpha,
  truncation = NULL,
  truncation_type = "lp"
)
```

Arguments

Cover	Numeric. Cover of the reinsurance layer.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.
t	Numeric vector. Thresholds of the piecewise Pareto distribution.
alpha	Numeric vector. $\alpha[i]$ is the Pareto alpha in excess of $t[i]$.
truncation	Numeric. If truncation is not NULL and $\text{truncation} > t$, then the Pareto distribution is truncated at truncation.

truncation_type

Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.

Value

The expected loss of the (truncated) piecewise Pareto distribution with parameter vectors `t` and `alpha` in the layer `Cover` vs `AttachmentPoint`

References

Riegel, U. (2018) Matching tower information with piecewise Pareto. *European Actuarial Journal* 8(2): 437–460

Examples

```
t <- c(1000, 2000, 3000)
alpha <- c(1, 1.5, 2)
PiecewisePareto_Layer_Mean(4000, 1000, t, alpha)
PiecewisePareto_Layer_Mean(4000, 1000, t, alpha, truncation = 5000)
PiecewisePareto_Layer_Mean(4000, 1000, t, alpha, truncation = 5000, truncation_type = "lp")
PiecewisePareto_Layer_Mean(4000, 1000, t, alpha, truncation = 5000, truncation_type = "wd")
```

PiecewisePareto_Layer_SM

Second Layer Moment of the Piecewise Pareto Distribution

Description

Calculates the second moment of a piecewise Pareto distribution in a reinsurance layer

Usage

```
PiecewisePareto_Layer_SM(
  Cover,
  AttachmentPoint,
  t,
  alpha,
  truncation = NULL,
  truncation_type = "lp"
)
```

Arguments

`Cover` Numeric. Cover of the reinsurance layer.
`AttachmentPoint` Numeric. Attachment point of the reinsurance layer.

t	Numeric vector. Thresholds of the piecewise Pareto distribution.
alpha	Numeric vector. alpha[i] is the Pareto alpha in excess of t[i].
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.
truncation_type	Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.

Value

The second moment of the (truncated) piecewise Pareto distribution with parameter vectors t and alpha in the layer Cover xs AttachmentPoint

Examples

```
t <- c(1000, 2000, 3000)
alpha <- c(1, 1.5, 2)
PiecewisePareto_Layer_SM(4000, 1000, t, alpha)
PiecewisePareto_Layer_SM(4000, 1000, t, alpha, truncation = 5000)
PiecewisePareto_Layer_SM(4000, 1000, t, alpha, truncation = 5000, truncation_type = "lp")
PiecewisePareto_Layer_SM(4000, 1000, t, alpha, truncation = 5000, truncation_type = "wd")
```

PiecewisePareto_Layer_Var

Layer Variance of the Piecewise Pareto Distribution

Description

Calculate the variance of a piecewise Pareto distribution in a reinsurance layer

Usage

```
PiecewisePareto_Layer_Var(
  Cover,
  AttachmentPoint,
  t,
  alpha,
  truncation = NULL,
  truncation_type = "lp"
)
```

Arguments

Cover	Numeric. Cover of the reinsurance layer.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.

t	Numeric vector. Thresholds of the piecewise Pareto distribution.
alpha	Numeric vector. alpha[i] is the Pareto alpha in excess of t[i].
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.
truncation_type	Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.

Value

The variance of the (truncated) piecewise Pareto distribution with parameter vectors t and alpha in the layer Cover xs AttachmentPoint

Examples

```
t <- c(1000, 2000, 3000)
alpha <- c(1, 1.5, 2)
PiecewisePareto_Layer_Var(4000, 1000, t, alpha)
PiecewisePareto_Layer_SM(4000, 1000, t, alpha) - PiecewisePareto_Layer_Mean(4000, 1000, t, alpha)^2
PiecewisePareto_Layer_Var(4000, 1000, t, alpha, truncation = 5000)
PiecewisePareto_Layer_Var(4000, 1000, t, alpha, truncation = 5000, truncation_type = "lp")
PiecewisePareto_Layer_Var(4000, 1000, t, alpha, truncation = 5000, truncation_type = "wd")
```

PiecewisePareto_Match_Layer_Losses

Match a Tower of Expected Layers Losses

Description

Matches the expected losses of a tower of reinsurance layers using a piecewise Pareto severity

Usage

```
PiecewisePareto_Match_Layer_Losses(
  Attachment_Points,
  Expected_Layer_Losses,
  Unlimited_Layers = FALSE,
  Frequencies = NULL,
  FQ_at_lowest_AttPt = NULL,
  FQ_at_highest_AttPt = NULL,
  TotalLoss_Frequencies = NULL,
  minimize_ratios = TRUE,
  Use_unlimited_Layer_for_FQ = TRUE,
  truncation = NULL,
  truncation_type = "lp",
  dispersion = 1,
```

```

    tolerance = 1e-10,
    alpha_max = 100,
    merge_tolerance = 1e-06,
    RoL_tolerance = 1e-06
)

```

Arguments

Attachment_Points	Numeric vector. Vector containing the attachment points of consecutive layers in increasing order
Expected_Layer_Losses	Numeric vector. Vector containing the expected losses of layers x s the attachment points.
Unlimited_Layers	Logical. If TRUE, then <code>Expected_Layer_Losses[i]</code> contains the expected loss of Inf x s <code>Attachment_Points[i]</code> . If FALSE then <code>Expected_Layer_Losses[i]</code> contains the expected loss of the layer <code>Attachment_Points[i+1]</code> x s <code>Attachment_Points[i]</code>
Frequencies	Numeric vector. Expected frequencies excess the attachment points. The vector may contain NAs. If NULL then the function calculates frequencies.
FQ_at_lowest_AttPt	Numerical. Expected frequency excess <code>Attachment_Points[1]</code> . Overrides first entry in <code>Frequencies</code> .
FQ_at_highest_AttPt	Numerical. Expected frequency excess <code>Attachment_Points[k]</code> . Overrides last entry in <code>Frequencies</code> .
TotalLoss_Frequencies	Numeric vector. <code>TotalLoss_Frequencies[i]</code> is the frequency of total losses to layer i (i.e. <code>Attachment_Points[i+1] - Attachment_Points[i]</code> x s <code>Attachment_Points[i]</code>). <code>TotalLoss_Frequencies[i]</code> is the frequency for losses larger than or equal to <code>Attachment_Points[i+1]</code> , whereas <code>Frequencies[i]</code> is the frequency of losses larger than <code>Attachment_Points[i]</code> . <code>TotalLoss_Frequencies[i] > Frequencies[i+1]</code> means that there is a point mass of the severity at <code>Attachment_Points[i+1]</code> .
minimize_ratios	Logical. If TRUE then ratios between alphas are minimized.
Use_unlimited_Layer_for_FQ	Logical. Only relevant if no frequency is provided for the highest attachment point by the user. If TRUE then the frequency is calculated using the Pareto alpha between the last two layers.
truncation	Numeric. If <code>truncation</code> is not NULL, then the distribution is truncated at <code>truncation</code> .
truncation_type	Character. If <code>truncation_type = "wd"</code> then the whole distribution is truncated. If <code>truncation_type = "lp"</code> then a truncated Pareto is used for the last piece.
dispersion	Numerical. Dispersion of the claim count distribution in the resulting <code>PPP_Model</code> .
tolerance	Numeric. Numerical tolerance.
alpha_max	Numerical. Maximum alpha to be used for the matching.

merge_tolerance	Numerical. Consecutive Pareto pieces are merged if the alphas deviate by less than merge_tolerance.
RoL_tolerance	Numerical. Consecutive layers are merged if RoL decreases less than factor 1 - RoL_tolerance.

Value

A PPP_Model object that contains the information about a collective model with a Panjer distributed claim count and a Piecewise Pareto distributed severity. The object contains the following elements:

- FQ Numerical. Frequency in excess of the lowest threshold of the piecewise Pareto distribution
- t Numeric vector. Vector containing the thresholds for the piecewise Pareto distribution
- alpha Numeric vector. Vector containing the Pareto alphas of the piecewise Pareto distribution
- truncation Numerical. If truncation is not NULL and truncation > max(t), then the distribution is truncated at truncation.
- truncation_type Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.
- dispersion Numerical. Dispersion of the Panjer distribution (i.e. variance to mean ratio).
- Status Numerical indicator: 0 = success, 1 = some information has been ignored, 2 = no solution found
- Comment Character. Information on whether the fit was successful

References

Riegel, U. (2018) Matching tower information with piecewise Pareto. *European Actuarial Journal* 8(2): 437–460

Examples

```
AP <- Example1_AP
EL <- Example1_EL
PiecewisePareto_Match_Layer_Losses(AP, EL)
EL_unlimited <- rev(cumsum(rev(Example1_EL)))
PiecewisePareto_Match_Layer_Losses(AP, EL_unlimited, Unlimited_Layers = TRUE)
PiecewisePareto_Match_Layer_Losses(AP, EL, FQ_at_lowest_AttPt = 0.5)
Example1_FQ <- c(0.3, 0.15, 0.08, 0.02, 0.005)
PiecewisePareto_Match_Layer_Losses(AP, EL, Frequencies = Example1_FQ)
```

 PiecewisePareto_ML_Estimator_Alpha

Maximum Likelihood Estimation of the Alphas of the Piecewise Pareto Distribution

Description

Calculates the maximum likelihood estimator of the parameter vector alpha for a piecewise Pareto distribution with given vector t and (if applicable) a known truncation

Usage

```
PiecewisePareto_ML_Estimator_Alpha(
  losses,
  t,
  truncation = NULL,
  truncation_type = "lp",
  reporting_thresholds = NULL,
  is.censored = NULL,
  weights = NULL,
  alpha_min = 0.001,
  alpha_max = 10
)
```

Arguments

losses	Numeric vector. Losses that are used for the ML estimation.
t	Numeric vector. Thresholds of the piecewise Pareto distribution.
truncation	Numeric. If truncation is not NULL and $\text{truncation} > \max(t)$, then the distribution is truncated at truncation.
truncation_type	Character. If <code>truncation_type = "wd"</code> then the whole distribution is truncated. If <code>truncation_type = "lp"</code> then a truncated Pareto is used for the last piece.
reporting_thresholds	Numeric vector. Allows to enter loss specific reporting thresholds. If NULL then all reporting thresholds are assumed to be less than or equal to $t[1]$.
is.censored	Logical vector. TRUE indicates that a loss has been censored by the policy limit. The assumption is that the uncensored losses are piecewise Pareto distributed with the alphas we are looking for. <code>is.censored = NULL</code> means that no losses are censored.
weights	Numeric vector. Weights for the losses. For instance <code>weights[i] = 2</code> and <code>weights[j] = 1</code> for $j \neq i$ has the same effect as adding another loss of size <code>loss[i]</code> .
alpha_min	Numeric. Lower bound for the estimated alphas (only used in truncated case).
alpha_max	Numeric. Upper bound for the estimated alphas (only used in truncated case).

Value

Maximum likelihood estimator for the parameter alpha of a Pareto distribution with threshold t given the observations losses

Examples

```
losses <- rPiecewisePareto(10000, t = c(100,200,300), alpha = c(1,2,3))
PiecewisePareto_ML_Estimator_Alpha(losses, c(100,200,300))

losses <- rPiecewisePareto(10000, t = c(100,200,300), alpha = c(1,2,3),
                           truncation = 500, truncation_type = "wd")
PiecewisePareto_ML_Estimator_Alpha(losses, c(100,200,300))
PiecewisePareto_ML_Estimator_Alpha(losses, c(100,200,300),
                                   truncation = 500, truncation_type = "wd")
reporting_thresholds <- rPareto(10000, 100, 3)
index <- losses > reporting_thresholds
losses <- losses[index]
reporting_thresholds <- reporting_thresholds[index]
PiecewisePareto_ML_Estimator_Alpha(losses, c(100,200,300),
                                   truncation = 500, truncation_type = "wd")
PiecewisePareto_ML_Estimator_Alpha(losses, c(100,200,300),
                                   truncation = 500, truncation_type = "wd",
                                   reporting_thresholds = reporting_thresholds)

losses <- c(140, 240, 490, 200, 110, 710, 120, 190, 210, 310)
w <- rep(1, length(losses))
w[1] <- 2
losses2 <- c(losses, losses[1])
PiecewisePareto_ML_Estimator_Alpha(losses, c(100,200,300), weights = w)
PiecewisePareto_ML_Estimator_Alpha(losses2, c(100,200,300))
```

PiecewisePareto_PDF *Density of the Piecewise Pareto Distribution*

Description

Calculates the density function of the piecewise Pareto distribution. This function is deprecated. Use dPiecewisePareto instead.

Usage

```
PiecewisePareto_PDF(x, t, alpha, truncation = NULL, truncation_type = "lp")
```

Arguments

x	Numeric. The function evaluates the density at x.
t	Numeric vector. Thresholds of the piecewise Pareto distribution.
alpha	Numeric vector. alpha[i] is the Pareto alpha in excess of t[i].

truncation Numeric. If truncation is not NULL and truncation > t, then the distribution is truncated at truncation.

truncation_type Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.

Value

Density function of the piecewise Pareto distribution with parameter vectors t and alpha evaluated at x

Examples

```
t <- c(1000, 2000, 3000)
alpha <- c(1, 1.5, 2)
x <- 0:10 * 1000
dPiecewisePareto(x, t, alpha)
dPiecewisePareto(x, t, alpha, truncation = 5000, truncation_type = "lp")
dPiecewisePareto(x, t, alpha, truncation = 5000, truncation_type = "wd")
```

pPareto

Distribution Function of the Pareto Distribution

Description

Calculates the cumulative distribution function of a Pareto distribution

Usage

```
pPareto(x, t, alpha, truncation = NULL)
```

Arguments

x Numeric. The function evaluates the CDF at x.

t Numeric. Threshold of the Pareto distribution.

alpha Numeric. Pareto alpha.

truncation Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

Distribution function of the Pareto distribution with parameters t and alpha evaluated at x

Examples

```
x <- 0:10 * 1000
pPareto(x, 1000, 2)
pPareto(x, 1000, 2, truncation = 5000)
```

pPiecewisePareto

Distribution Function of the Piecewise Pareto Distribution

Description

Calculates the cumulative distribution function of a Piecewise Pareto Distribution

Usage

```
pPiecewisePareto(x, t, alpha, truncation = NULL, truncation_type = "lp")
```

Arguments

x	Numeric. The function evaluates the CDF at x.
t	Numeric vector. Thresholds of the piecewise Pareto distribution.
alpha	Numeric vector. alpha[i] is the Pareto alpha in excess of t[i].
truncation	Numeric. If truncation is not NULL and truncation > t, then the distribution is truncated at truncation.
truncation_type	Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.

Value

Distribution function of the piecewise Pareto distribution with parameter vectors t and alpha evaluated at x

References

Riegel, U. (2018) Matching tower information with piecewise Pareto. *European Actuarial Journal* 8(2): 437–460

Examples

```
t <- c(1000, 2000, 3000)
alpha <- c(1, 1.5, 2)
x <- 0:10 * 1000
pPiecewisePareto(x, t, alpha)
pPiecewisePareto(x, t, alpha, truncation = 5000, truncation_type = "lp")
pPiecewisePareto(x, t, alpha, truncation = 5000, truncation_type = "wd")
```

 PPP_Model

PPP_Model (Collective Panjer & Piecewise Pareto Model) Object

Description

Constructor function for the PPP_Model object

Usage

```

PPP_Model(
  FQ = NULL,
  t = NULL,
  alpha = NULL,
  truncation = NULL,
  truncation_type = "lp",
  dispersion = 1,
  Status = 0,
  Comment = "OK"
)

```

Arguments

FQ	Numerical. Expected claim count of the collective model.
t	Numeric vector. Vector containing the thresholds of the Piecewise Pareto distribution.
alpha	Numeric vector. Vector containing the alphas of the Piecewise Pareto distribution.
truncation	Numerical. If truncation is not NULL and $\text{truncation} > \max(t)$, then the distribution is truncated at truncation.
truncation_type	Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.
dispersion	Numerical. Dispersion of the Panjer distribution (i.e. variance to mean ratio).
Status	Numerical indicator if a function returns a PPP_Model object: 0 = success, 1 = some information has been ignored, 2 = no solution found
Comment	Charakter. An optional comment.

Examples

```

PPPM <- PPP_Model(2, c(1000,2000), c(1,2), dispersion = 2)
PPPM

```

PPP_Model_Excess_Frequency

Expected Frequency in Excess of a Threshold

Description

Calculates the expected frequency in excess of a threshold for a PPP_Model

Usage

```
PPP_Model_Excess_Frequency(x, PPP_Model)
```

Arguments

x Numeric. Threshold.
PPP_Model PPP_Model object.

Value

The expected frequency in excess of x for the given PPP_Model

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)  
PPPM  
Excess_Frequency(PPPM, c(-Inf, 0, 1000, 2000, 3000, Inf))
```

PPP_Model_Exp_Layer_Loss

Expected Loss of a Reinsurance Layer

Description

Calculates the expected loss of a reinsurance layer for a PPP_Model. This function is deprecated.
Use Layer_Mean instead.

Usage

```
PPP_Model_Exp_Layer_Loss(Cover, AttachmentPoint, PPP_Model)
```

Arguments

Cover Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint Numeric. Attachment point of the reinsurance layer.
PPP_Model PPP_Model object.

Value

The expected loss of the layer Cover xs AttachmentPoint for the given PPP_Model

Examples

```

PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Example1_AP
Example1_Cov
Example1_EL
Layer_Mean(PPPM, Example1_Cov, Example1_AP)

```

PPP_Model_Layer_Sd *Standard Deviation of a Reinsurance Layer*

Description

Calculates the standard deviation of the loss in a reinsurance layer for a PPP_Model

Usage

```
PPP_Model_Layer_Sd(Cover, AttachmentPoint, PPP_Model)
```

Arguments

Cover	Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint	Numeric. Attachment point of the reinsurance layer.
PPP_Model	PPP_Model object.

Value

The standard deviation of the loss in the layer Cover xs AttachmentPoint for the given PPP_Model

Examples

```

PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Layer_Sd(PPPM, Example1_Cov, Example1_AP)

```

PPP_Model_Layer_Var *Variance of a Reinsurance Layer*

Description

Calculates the variance of the loss in a reinsurance layer for a PPP_Model. This function is deprecated. Use Layer_Var instead.

Usage

```
PPP_Model_Layer_Var(Cover, AttachmentPoint, PPP_Model)
```

Arguments

Cover Numeric. Cover of the reinsurance layer. Use Inf for unlimited layers.
AttachmentPoint Numeric. Attachment point of the reinsurance layer.
PPP_Model PPP_Model object.

Value

The variance of the loss in the layer Cover xs AttachmentPoint for the given PPP_Model

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(Example1_AP, Example1_EL)
PPPM
Example1_Cov <- c(diff(Example1_AP), Inf)
Layer_Var(PPPM, Example1_Cov, Example1_AP)
```

PPP_Model_Simulate *Simulate Losses with a PPP_Model*

Description

Simulates losses of a PPP_Model

Usage

```
PPP_Model_Simulate(n, PPP_Model)
```

Arguments

n Integer. Number of Simulations.
PPP_Model PPP_Model object.

Value

A matrix where row k contains the simulated losses of the kth simulation.

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(c(1000, 2000, 3000), c(2000, 1000, 500),
                                          truncation = 10000, truncation_type = "wd")
PPPM
Simulate_Losses(PPPM, 100)
```

print.PGP_Model	<i>Print a PGP_Model Object(Collective Panjer & Generalized Pareto Model) Object</i>
-----------------	--

Description

Print method for PGP_Model objects

Usage

```
## S3 method for class 'PGP_Model'
print(x, ...)
```

Arguments

x	PGP_Model object.
...	Other arguments, all currently ignored.

print.PPP_Model	<i>Print a PPP_Model Object(Collective Panjer & Piecewise Pareto Model) Object</i>
-----------------	--

Description

Print method for PPP_Model objects

Usage

```
## S3 method for class 'PPP_Model'
print(x, ...)
```

Arguments

x	PPP_Model object.
...	Other arguments, all currently ignored.

qGenPareto

Quantile Function of the generalized Pareto Distribution

Description

Calculates the quantile function of a generalized Pareto distribution

Usage

```
qGenPareto(p, t, alpha_ini, alpha_tail, truncation = NULL)
```

Arguments

p	Numeric. The function evaluates the inverse CDF at p.
t	Numeric. Threshold of the piecewise Pareto distribution.
alpha_ini	Numeric. Initial Pareto alpha.
alpha_tail	Numeric. Tail Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the generalized Pareto distribution is truncated at truncation.

Value

Quantile function of the Pareto distribution with parameters t, alpha_ini and alpha_tail, evaluated at p

Examples

```
p <- 0:10 * 0.1
qGenPareto(p, 1000, 2, 3)
qGenPareto(p, 1000, 2, 3, truncation = 5000)
```

qPareto

Quantile Function of the Pareto Distribution

Description

Calculates the quantile function of a Pareto distribution

Usage

```
qPareto(p, t, alpha, truncation = NULL)
```

Arguments

p	Numeric. The function evaluates the inverse CDF at p.
t	Numeric. Threshold of the piecewise Pareto distribution.
alpha	Numeric. Pareto alpha.
truncation	Numeric. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation.

Value

Quantile function of the Pareto distribution with parameters t and alpha, evaluated at p

Examples

```
p <- 0:10 * 0.1
qPareto(p, 1000, 2)
qPareto(p, 1000, 2, truncation = 5000)
```

qPiecewisePareto *Quantile Function of the Piecewise Pareto Distribution*

Description

Calculates the quantile function of a piecewise Pareto distribution

Usage

```
qPiecewisePareto(p, t, alpha, truncation = NULL, truncation_type = "lp")
```

Arguments

p	Numeric. The function evaluates the quantile function at p.
t	Numeric vector. Thresholds of the piecewise Pareto distribution.
alpha	Numeric vector. alpha[i] is the Pareto alpha in excess of t[i].
truncation	Numeric. If truncation is not NULL and truncation > t, then the distribution is truncated at truncation.
truncation_type	Character. If truncation_type = "wd" then the whole distribution is truncated. If truncation_type = "lp" then a truncated Pareto is used for the last piece.

Value

Quantile function of the piecewise Pareto distribution with parameter vectors t and alpha evaluated at p

Examples

```
t <- c(1000, 2000, 3000)
alpha <- c(1, 1.5, 2)
p <- 0:10 * 0.1
qPiecewisePareto(p, t, alpha)
qPiecewisePareto(p, t, alpha, truncation = 5000, truncation_type = "lp")
qPiecewisePareto(p, t, alpha, truncation = 5000, truncation_type = "wd")
```

rGenPareto

Simulation of the generalized Pareto Distribution

Description

Generates random deviates of a generalized Pareto distribution

Usage

```
rGenPareto(n, t, alpha_ini, alpha_tail, truncation = NULL)
```

Arguments

n	Numeric. Number of observations.
t	Numeric vector. Thresholds of the generalized Pareto distributions
alpha_ini	Numeric vector. Initial Pareto alphas of the generalized Pareto distributions.
alpha_tail	Numeric vector. Tail Pareto alphas of the generalized Pareto distributions.
truncation	NULL or Numeric vector. If truncation is not NULL and truncation > t, then the generalized Pareto distributions are truncated at truncation (resampled generalized Pareto)

Value

A vector of n samples from the (truncated) generalized Pareto distribution with parameters t, alpha_ini and alpha_tail

Examples

```
rGenPareto(100, 1000, 2, 3)
rGenPareto(100, 1000, 2, 3, truncation = 2000)
rGenPareto(100, t = c(1, 10, 100, 1000), alpha_ini = 1, alpha_tail = c(2, 5))
```

rPareto *Simulation of the Pareto Distribution*

Description

Generates random deviates of a Pareto distribution

Usage

```
rPareto(n, t, alpha, truncation = NULL)
```

Arguments

n	Numeric. Number of observations.
t	Numeric vector. Thresholds of the Pareto distributions
alpha	Numeric vector. Pareto alphas of the Pareto distributions.
truncation	NULL or Numeric vector. If truncation is not NULL and truncation > t, then the Pareto distribution is truncated at truncation (resampled Pareto)

Value

A vector of n samples from the (truncated) Pareto distribution with parameters t and alpha

Examples

```
rPareto(100, 1000, 2)
rPareto(100, 1000, 2, truncation = 2000)
rPareto(100, t = c(1, 10, 100, 1000, 10000), alpha = c(1, 2, 4, 8, 16))
```

rPiecewisePareto *Simulation of the Piecewise Pareto Distribution*

Description

Generates random deviates of a piecewise Pareto distribution

Usage

```
rPiecewisePareto(
  n,
  t,
  alpha,
  truncation = NULL,
  truncation_type = "lp",
  scale_pieces = NULL
)
```

Arguments

n	Numeric. Number of simulations
t	Numeric vector. Thresholds of the piecewise Pareto distribution.
alpha	Numeric vector. $\alpha[i]$ is the Pareto alpha in excess of $t[i]$.
truncation	Numeric. If truncation is not NULL and $\text{truncation} > t$, then the distribution is truncated at truncation.
truncation_type	Character. If $\text{truncation_type} = \text{"wd"}$ then the whole distribution is truncated. If $\text{truncation_type} = \text{"lp"}$ then a truncated Pareto is used for the last piece.
scale_pieces	Numeric vector. If not NULL then the density of the i -th Pareto piece (on the interval $(t[i], t[i+1])$) is scaled with the factor $\text{const} * \text{scale_pieces}[i]$ (where const is a normalization constant)

Value

A vector of n samples from the (truncated) piecewise Pareto distribution with parameter vectors t and α

Examples

```
t <- c(1000, 2000, 3000)
alpha <- c(1, 1.5, 2)
rPiecewisePareto(100, t, alpha)
rPiecewisePareto(100, t, alpha, truncation = 5000)
rPiecewisePareto(100, t, alpha, truncation = 5000, truncation_type = "lp")
rPiecewisePareto(100, t, alpha, truncation = 5000, truncation_type = "wd")
```

 Simulate_Losses

Simulate Losses with a Collective Model

Description

Simulates losses with a collective model

Usage

```
Simulate_Losses(CollectiveModel, nyears = 1)
```

Arguments

CollectiveModel	A collective model object. Currently only PPP_Models are handled.
nyears	Integer. Number of simulated years.

Value

A matrix where row k contains the simulated losses of the kth simulated year.

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(c(1000, 2000, 3000), c(2000, 1000, 500),
                                           truncation = 10000, truncation_type = "wd")
PPPM
Simulate_Losses(PPPM, 100)
```

Simulate_Losses.PGP_Model

Simulate Losses with a PGP_Model

Description

Simulates losses with a PGP_Model

Usage

```
## S3 method for class 'PGP_Model'
Simulate_Losses(CollectiveModel, nyears = 1)
```

Arguments

CollectiveModel
PGP_Model object.

nyears Integer. Number of simulated years.

Value

A matrix where row k contains the simulated losses of the kth simulated year.

Examples

```
PGPM <- PGP_Model(2, 1000, 1, 2, dispersion = 2)
PGPM
Simulate_Losses(PGPM, 100)
```

`Simulate_Losses.PPP_Model`*Simulate Losses with a PPP_Model*

Description

Simulates losses with a PPP_Model

Usage

```
## S3 method for class 'PPP_Model'  
Simulate_Losses(CollectiveModel, nyears = 1)
```

Arguments

`CollectiveModel`
PPP_Model object.
`nyears` Integer. Number of simulated years.

Value

A matrix where row k contains the simulated losses of the kth simulated year.

Examples

```
PPPM <- PiecewisePareto_Match_Layer_Losses(c(1000, 2000, 3000), c(2000, 1000, 500),  
                                          truncation = 10000, truncation_type = "wd")  
PPPM  
Simulate_Losses(PPPM, 100)
```

Index

* datasets

- Example1_AP, 5
- Example1_EL, 6

- dGenPareto, 3
- dPareto, 4
- dPiecewisePareto, 4

- Example1_AP, 5
- Example1_EL, 6
- Excess_Frequency, 6
- Excess_Frequency.PGP_Model, 7
- Excess_Frequency.PPP_Model, 7

- Fit_PML_Curve, 8
- Fit_References, 9

- GenPareto_Layer_Mean, 12
- GenPareto_Layer_SM, 13
- GenPareto_Layer_Var, 14
- GenPareto_ML_Estimator_Alpha, 15

- is.PGP_Model, 16
- is.PPP_Model, 17
- is.valid.PGP_Model, 18
- is.valid.PPP_Model, 18

- Layer_Mean, 19
- Layer_Mean.PGP_Model, 20
- Layer_Mean.PPP_Model, 20
- Layer_Sd, 21
- Layer_Sd.PGP_Model, 22
- Layer_Sd.PPP_Model, 23
- Layer_Var, 23
- Layer_Var.PGP_Model, 24
- Layer_Var.PPP_Model, 25
- Local_Pareto_Alpha, 26

- Pareto_CDF, 27
- Pareto_Extrapolation, 27
- Pareto_Find_Alpha_bt看_FQ_Layer, 30

- Pareto_Find_Alpha_bt看_FQs, 29
- Pareto_Find_Alpha_bt看_Layers, 31
- Pareto_Layer_Mean, 32
- Pareto_Layer_SM, 33
- Pareto_Layer_Var, 33
- Pareto_ML_Estimator_Alpha, 34
- Pareto_PDF, 36
- pGenPareto, 36
- PGP_Model, 37
- PiecewisePareto_CDF, 38
- PiecewisePareto_Layer_Mean, 39
- PiecewisePareto_Layer_SM, 40
- PiecewisePareto_Layer_Var, 41
- PiecewisePareto_Match_Layer_Losses, 42
- PiecewisePareto_ML_Estimator_Alpha, 45
- PiecewisePareto_PDF, 46
- pPareto, 47
- pPiecewisePareto, 48
- PPP_Model, 49
- PPP_Model_Excess_Frequency, 50
- PPP_Model_Exp_Layer_Loss, 50
- PPP_Model_Layer_Sd, 51
- PPP_Model_Layer_Var, 52
- PPP_Model_Simulate, 52
- print.PGP_Model, 53
- print.PPP_Model, 53

- qGenPareto, 54
- qPareto, 54
- qPiecewisePareto, 55

- rGenPareto, 56
- rPareto, 57
- rPiecewisePareto, 57

- Simulate_Losses, 58
- Simulate_Losses.PGP_Model, 59
- Simulate_Losses.PPP_Model, 60