

# Package ‘bmem’

September 20, 2020

**Type** Package

**Title** Mediation Analysis with Missing Data Using Bootstrap

**Version** 1.8

**Date** 2020-09-18

**Author** Zhiyong Zhang and Lijuan Wang

**Maintainer** Zhiyong Zhang <zhiyongzhang@nd.edu>

**Depends** R (>= 1.7), Amelia, MASS, snowfall

**Imports** lavaan, sem

## Description

Four methods for mediation analysis with missing data: Listwise deletion, Pairwise deletion, Multiple imputation, and Two Stage Maximum Likelihood algorithm. For MI and TS-ML, auxiliary variables can be included. Bootstrap confidence intervals for mediation effects are obtained. The robust method is also implemented for TS-ML. Since version 1.4, bmem adds the capability to conduct power analysis for mediation models. Details about the methods used can be found in these articles. Zhang and Wang (2003) <doi:10.1007/s11336-012-9301-5>. Zhang (2014) <doi:10.3758/s13428-013-0424-0>.

**License** GPL-2

**LazyLoad** yes

**URL** <https://bigdatalab.nd.edu>

**ZipData** no

**NeedsCompilation** no

**Repository** CRAN

**Date/Publication** 2020-09-19 22:20:26 UTC

## R topics documented:

bmem-package	3
bmem	3
bmem.bs	4
bmem.ci.bc	5

bmem.ci.bc1 . . . . .	6
bmem.ci.bca . . . . .	7
bmem.ci.bca1 . . . . .	7
bmem.ci.norm . . . . .	8
bmem.ci.p . . . . .	9
bmem.cov . . . . .	9
bmem.em . . . . .	10
bmem.em.boot . . . . .	10
bmem.em.cov . . . . .	11
bmem.em.jack . . . . .	12
bmem.em.rcov . . . . .	12
bmem.list . . . . .	13
bmem.list.boot . . . . .	14
bmem.list.cov . . . . .	14
bmem.list.jack . . . . .	15
bmem.mi . . . . .	15
bmem.mi.boot . . . . .	16
bmem.mi.cov . . . . .	16
bmem.mi.jack . . . . .	17
bmem.moments . . . . .	17
bmem.pair . . . . .	18
bmem.pair.boot . . . . .	18
bmem.pair.cov . . . . .	19
bmem.pair.jack . . . . .	19
bmem.pattern . . . . .	20
bmem.plot . . . . .	20
bmem.raw2cov . . . . .	21
bmem.sem . . . . .	21
bmem.sobel . . . . .	22
bmem.sobel.ind . . . . .	23
bmem.ssq . . . . .	23
bmem.v . . . . .	24
plot.bmem . . . . .	24
popPar . . . . .	25
power.basic . . . . .	25
power.boot . . . . .	27
power.curve . . . . .	29
summary.bmem . . . . .	31
summary.power . . . . .	31

---

 bmem-package

*Mediation analysis with missing data using bootstrap*


---

### Description

Four methods for mediation analysis with missing data: Listwise deletion, Pairwise deletion, Multiple imputation, and Two-stage ML. For MI and TSML, auxiliary variables can be included. Bootstrap confidence intervals for mediation effects are obtained.

### Details

Package: bmem  
 Type: Package  
 Version: 1.0  
 Date: 2011-01-04  
 License: GPL-2  
 LazyLoad: yes

### Author(s)

Zhiyong Zhang and Lijuan Wang

Maintainer: Zhiyong Zhang <zhiyongzhang@nd.edu>

---

 bmem

*Mediation analysis based on bootstrap*


---

### Description

Mediation analysis based on bootstrap

### Usage

```

bmem(x, ram, indirect, v, method='tsml', ci='bc', cl=.95,
      boot=1000, m=10, varphi=.1, st='i', robust=FALSE,
      max_it=500, moment=FALSE, ...)
  
```

### Arguments

x                    A data set  
 ram                  RAM path for the mediaiton model  
 indirect            A vector of indirect effec

v	Indices of variables used in the mediation model. If omitted, all variables are used.
method	list: listwise deletion, pair: pairwise deletion, mi: multiple imputation, em: EM algorithm.
ci	norm: normal approximation CI, perc: percentile CI, bc: bias-corrected CI, bca: BCa
cl	Confidence level. Can be a vector.
boot	Number of bootstraps
m	Number of imputations
varphi	Percent of data to be downweighted
st	Starting values
robust	Robust method
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
max_it	Maximum number of iterations in EM
...	Other options for <a href="#">sem</a> function can be used.

### Details

The indirect effect can be specified using equations such as  $a*b$ ,  $a*b+c$ , and  $a*b*c+d*e+f$ . A vector of indirect effects can be used `indirect=c('a*b', 'a*b+c')`.

### Value

The on-screen output includes the parameter estimates, bootstrap standard errors, and CIs.

### Author(s)

Zhiyong Zhang and Lijuan Wang

### References

Zhang, Z., & Wang, L. (2013). Methods for mediation analysis with missing data. *Psychometrika*, 78(1), 154-184.

---

bmem.bs

*Bootstrap but using the Bollen-Stine method*

---

### Description

The same as [bmem](#) but using the Bollen-Stine method

### Usage

```
bmem.bs(x, ram, indirect, v, ci='bc', cl=.95,
        boot=1000, max_it=500, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
v	Indices of variables used in the mediation model. If omitted, all variables are used.
ci	norm: normal approximation CI, perc: percentile CI, bc: bias-corrected CI, bca: BCa
c1	Confidence level. Can be a vector.
boot	Number of bootstraps
max_it	Maximum number of iterations in EM
...	Other options for <a href="#">sem</a> function can be used.

**Value**

The on-screen output includes the parameter estimates, bootstrap standard errors, and CIs.

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**References**

- Zhang, Z. & Wang, L. (2011) Four methods for mediation analysis with missing data.  
 Zhang, Z. (2011) Robust mediation analysis with missing data and auxiliary variables.

**See Also**

[bmem](#), [bmem.sobel](#), [bmem.plot](#)

---

bmem.ci.bc

*Bias-corrected confidence intervals*

---

**Description**

Bias-corrected confidence intervals

**Usage**

```
bmem.ci.bc(par.boot, par0, c1=.95)
```

**Arguments**

par.boot	A bootstrap object.
par0	Original estimate
c1	Confidence level. Default 0.95.

**Value**

BC confidence intervals. The output includes - estimates, bootstrap standard errors, and confidence intervals.

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**See Also**

[bmem.ci.norm](#), [bmem.ci.p](#), [bmem.ci.bca](#)

---

bmem.ci.bc1

*Bias-corrected confidence intervals (for a single variable)*

---

**Description**

Bias-corrected confidence intervals (for a single variable)

**Usage**

```
bmem.ci.bc1(x, b, cl = 0.95)
```

**Arguments**

x	A vector from a bootstrap output.
b	Parameter estimate from the original sample
cl	Confidence level. Default 0.95.

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**See Also**

[bmem.ci.norm](#), [bmem.ci.p](#), [bmem.ci.bca](#)

---

`bmem.ci.bca`*Bias-corrected and accelerated confidence intervals*

---

**Description**

Bias-corrected and accelerated confidence intervals

**Usage**

```
bmem.ci.bca(par.boot, par0, jack, cl = 0.95)
```

**Arguments**

<code>par.boot</code>	A bootstrap object.
<code>par0</code>	Original estimate
<code>jack</code>	A Jackknife object.
<code>cl</code>	Confidence level. Default 0.95.

**Value**

BCa confidence intervals. The output includes - estimates, bootstrap standard errors, and confidence intervals.

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**See Also**

[bmem.ci.norm](#), [bmem.ci.p](#), [bmem.ci.bc](#), [bmem.list.jack](#), [bmem.pair.jack](#), [bmem.mi.jack](#), [bmem.em.jack](#),

---

`bmem.ci.bca1`*BCa for a single variable*

---

**Description**

BCa for a single variable

**Usage**

```
bmem.ci.bca1(x, b, jack, cl = 0.95)
```

**Arguments**

x	A vector from a bootstrap output.
b	Parameter estimate from the original sample
jack	A vector from a Jackknife analysis
cl	Confidence level. Default 0.95.

---

`bmem.ci.norm`*Confidence interval based on normal approximation*

---

**Description**

Confidence interval based on normal approximation

**Usage**

```
bmem.ci.norm(par.boot, par0, cl = 0.95)
```

**Arguments**

par.boot	A bootstrap object.
par0	Original estimate
cl	Confidence level. Default 0.95.

**Value**

Normal confidence intervals. The output includes - estimates, bootstrap standard errors, and confidence intervals.

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**See Also**

[bmem.ci.bca](#), [bmem.ci.p](#), [bmem.ci.bc](#)



---

bmem.ci.p	<i>Percentile confidence interval</i>
-----------	---------------------------------------

---

**Description**

Percentile confidence interval

**Usage**

```
bmem.ci.p(par.boot, par0, cl = 0.95)
```

**Arguments**

par.boot	A bootstrap object.
par0	Original estimate
cl	Confidence level. Default 0.95.

**Value**

Percentile confidence intervals. The output includes - estimates, bootstrap standard errors, and confidence intervals.

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**See Also**

[bmem.ci.bca](#), [bmem.ci.norm](#), [bmem.ci.bc](#)

---

bmem.cov	<i>Calculate the covariance matrix based on a given ram model</i>
----------	---

---

**Description**

Can be used to simulated data for an SEM model.

**Usage**

```
bmem.cov(ram,obs.variables,moment=FALSE, debug=FALSE)
```

**Arguments**

ram	An ram model
obs.variables	Names of the observed variables
moment	Whether to use the mean structure
debug	debug mode

---

 bmem.em

*Estimate a mediation model based on EM covariance matrix*


---

### Description

Estimate a mediation model based on EM covariance matrix

### Usage

```
bmem.em(x, ram, indirect, v, robust = FALSE,
        varphi = 0.1, st= "i", moment = FALSE,
        max_it = 500, ...)
```

### Arguments

x	A data set
ram	RAM path for the mediaiton model
indirect	A vector of indirect effec
v	Indices of variables used in the mediation model. If omitted, all variables are used.
robust	Roubst method
varphi	Percent of data to be downweighted
st	Starting values
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
max_it	Maximum number of iterations in EM
...	Other options for <a href="#">sem</a> function can be used.

---

 bmem.em.boot

*Bootstrap for EM*


---

### Description

Bootstrap for EM

### Usage

```
bmem.em.boot(x, ram, indirect, v, robust = FALSE,
            varphi = 0.1, st= "i", boot = 1000,
            moment = FALSE, max_it = 500, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
v	Indices of variables used in the mediation model. If omitted, all variables are used.
robust	Robust method
varphi	Percent of data to be downweighted
st	Starting values
boot	Number of bootstraps. Default is 1000.
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
max_it	Maximum number of iterations in EM
...	Other options for <a href="#">sem</a> function can be used.

**Details**

The indirect effect can be specified using equations such as  $a*b$ ,  $a*b+c$ , and  $a*b*c+d*e+f$ . A vector of indirect effects can be used `indirect=c('a*b', 'a*b+c')`.

**Value**

par.boot	Parameter estimates from bootstrap samples
par0	Parameter estimates from the original samples

**Author(s)**

Zhiyong Zhang and Lijuan Wang

---

bmem.em.cov

*Covariance matrix from EM*


---

**Description**

Covariance matrix from EM

**Usage**

```
bmem.em.cov(xmis, moment = FALSE, max_it = 500)
```

**Arguments**

xmis	An object from output of <a href="#">bmem.pattern</a> .
moment	Whether estimating mean
max_it	Maximum number of iterations

---

bmem.em.jack	<i>Jackknife estimate using EM</i>
--------------	------------------------------------

---

**Description**

Jackknife estimate using EM

**Usage**

```
bmem.em.jack(x, ram, indirect, v, robust = FALSE,
             varphi = 0.1, st= "i", moment = FALSE,
             max_it = 500, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
v	Indices of variables used in the mediation model. If omitted, all variables are used.
robust	Robust method
varphi	Percent of data to be downweighted
st	Starting values
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
max_it	Maximum number of iterations in EM
...	Other options for <a href="#">sem</a> function can be used.

---

bmem.em.rcov	<i>Estimation of robust covariance matrix</i>
--------------	---

---

**Description**

Estimation of robust covariance matrix

**Usage**

```
bmem.em.rcov(xmis, varphi=.1, moment=FALSE, max_it=1000, st='i')
```

**Arguments**

xmis	Missing data pattern
varphi	Percent of data to be downweighted
moment	Moment analysis if TRUE
max_it	Maximum number of iteration
st	Starting values

**Value**

An interval function to calculate the robust covaraince matrix

**Author(s)**

Zhiyong Zhang and Lijuan Wang

---

bmem.list

*Estimate a mediaiton model based on listwise deletion*


---

**Description**

Estimate a mediaiton model based on listwise deletion

**Usage**

```
bmem.list(x, ram, indirect, moment = FALSE, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediaiton model
indirect	A vector of indirect effec
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
...	Other options for <a href="#">sem</a> function can be used.

---

bmem.list.boot      *Bootstrap for listwise deletion method*

---

### Description

Bootstrap for listwise deletion method

### Usage

```
bmem.list.boot(x, ram, indirect, boot = 1000, moment = FALSE, ...)
```

### Arguments

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
boot	Number of bootstraps. Default is 1000.
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
...	Other options for <a href="#">sem</a> function can be used.

---

bmem.list.cov      *Covariance matrix for listwise deletion*

---

### Description

Covariance matrix for listwise deletion

### Usage

```
bmem.list.cov(x, moment = FALSE)
```

### Arguments

x	A data set
moment	Estimate mean or not

---

bmem.list.jack	<i>Jackknife for listwise deletion</i>
----------------	--

---

**Description**

Jackknife for listwise deletion

**Usage**

```
bmem.list.jack(x, ram, indirect, moment = FALSE, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
...	Other options for <a href="#">sem</a> function can be used.

---

bmem.mi	<i>Estimate a mediation model based on multiple imputation</i>
---------	--

---

**Description**

Estimate a mediation model based on multiple imputation

**Usage**

```
bmem.mi(x, ram, indirect, v, m = 10, moment = FALSE, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
v	Indices of variables used in the mediation model. If omitted, all variables are used.
m	Number of imputations.
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
...	Other options for <a href="#">sem</a> function can be used.

---

bmem.mi.boot                      *Bootstrap for multiple imputation*

---

### Description

Bootstrap for multiple imputation

### Usage

```
bmem.mi.boot(x, ram, indirect, v, m = 10, boot = 1000,
             moment = FALSE, ...)
```

### Arguments

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
v	Indices of variables used in the mediation model. If omitted, all variables are used.
m	Number of imputations
boot	Number of bootstraps. Default is 1000.
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
...	Other options for <a href="#">sem</a> function can be used.

---

bmem.mi.cov                      *Covariance estimation for multiple imputation*

---

### Description

Covariance estimation for multiple imputation

### Usage

```
bmem.mi.cov(x, m = 10, moment = FALSE)
```

### Arguments

x	A data set
m	Number of imputations
moment	Estimate mean or not



---

bmem.mi.jack	<i>Jackknife for multiple imputation</i>
--------------	--

---

**Description**

Jackknife for multiple imputation

**Usage**

```
bmem.mi.jack(x, ram, indirect, v, m = 10, moment = FALSE, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
v	Indices of variables used in the mediation model. If omitted, all variables are used.
m	Number of imputations.
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
...	Other options for <a href="#">sem</a> function can be used.

---

bmem.moments	<i>Calculate the moments of a data set</i>
--------------	--

---

**Description**

Calculate the moments of a data set using either listwise deletion or pairwise deletion

**Usage**

```
bmem.moments(x, type=0)
```

**Arguments**

x	A data set
type	How to deal with missing data. 0: listwise deletion; 1: pairwise deletion

---

bmem.pair	<i>Estimate a mediaton model based on pairwise deletion</i>
-----------	---

---

**Description**

Estimate a mediaton model based on pairwise deletion

**Usage**

```
bmem.pair(x, ram, indirect, moment = FALSE, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediaton model
indirect	A vector of indirect effec
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
...	Other options for <a href="#">sem</a> function can be used.

---

bmem.pair.boot	<i>Bootstrap for pairwise deletion</i>
----------------	--

---

**Description**

Bootstrap for pairwise deletion

**Usage**

```
bmem.pair.boot(x, ram, indirect, boot = 1000, moment = FALSE, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediaton model
indirect	A vector of indirect effec
boot	Number of bootstraps. Default is 1000.
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
...	Other options for <a href="#">sem</a> function can be used.

---

 bmem.pair.cov

*Covariance matrix estimation based on pairwise deletion*


---

**Description**

Covariance matrix estimation based on pairwise deletion

**Usage**

```
bmem.pair.cov(x, moment = FALSE)
```

**Arguments**

x	A data set
moment	Estimate mean or not

---

 bmem.pair.jack

*Jackknife for pairwise deletion*


---

**Description**

Jackknife for pairwise deletion

**Usage**

```
bmem.pair.jack(x, ram, indirect, moment = FALSE, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
moment	Select mean structure or covariance analysis. moment=FALSE, covariance analysis. moment=TRUE, mean and covariance analysis.
...	Other options for <a href="#">sem</a> function can be used.

---

bmem.pattern	<i>Obtain missing data pattern information</i>
--------------	--

---

**Description**

Obtain missing data pattern information

**Usage**

```
bmem.pattern(x)
```

**Arguments**

x	A data set
---	------------

---

bmem.plot	<i>Plot of the bootstrap distribution. This function is replaced by plot.</i>
-----------	---

---

**Description**

Plot of the bootstrap distribution

**Usage**

```
bmem.plot(x, par, ...)
```

**Arguments**

x	A bmem object
par	Name of parameter to be plotted.
...	Options used for the generic plot function.

**Value**

A plot

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**References**

Zhang, Z. & Wang, L. (2011) Four methods for mediation analysis with missing data.  
Zhang, Z. (2011) Robust mediation analysis with missing data and auxiliary variables.

**See Also**

[bmem](#), [bmem.sobel](#), [bmem.plot](#)

---

bmem.raw2cov	<i>Convert a raw moment matrix to covariance matrix</i>
--------------	---

---

**Description**

Convert a raw moment matrix to covariance matrix

**Usage**

```
bmem.raw2cov(x)
```

**Arguments**

x                    A moment matrix

**Value**

A covariance matrix

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**References**

Zhang, Z. & Wang, L. (2011) Four methods for mediation analysis with missing data.

Zhang, Z. (2011) Robust mediation analysis with missing data and auxiliary variables.

**See Also**

[bmem](#), [bmem.sobel](#), [bmem.plot](#)

---

bmem.sem	<i>Estimate a mediaiton model using SEM technique</i>
----------	---

---

**Description**

Estimate a mediaiton model using SEM technique

**Usage**

```
bmem.sem(x, ram, N, indirect, moment=FALSE, ...)
```

**Arguments**

x	A covariance matrix
ram	A path diagram from <code>specify.model</code>
N	Sample size
indirect	A vector of indirect effects
moment	Whether mean structure is used. The default is FALSE
...	Options that can be supplied to function <code>sem</code> .

**See Also**

[bmem.list.cov](#), [bmem.pair.cov](#), [bmem.mi.cov](#), [bmem.em.cov](#)

---

bmem.sobel

*Mediation analysis using sobel test (for complete data only)*

---

**Description**

Mediation analysis using sobel test (for complete data only)

**Usage**

```
bmem.sobel(x, ram, indirect, moment=FALSE, ...)
```

**Arguments**

x	A data set
ram	RAM path for the mediation model
indirect	A vector of indirect effects
moment	Covariance or moment analysis
...	Other options for <code>sem</code> function can be used.

**Value**

The on-screen output includes the parameter estimates and sobel standard errors.

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**References**

Zhang, Z. & Wang, L. (2011) Four methods for mediation analysis with missing data.  
 Zhang, Z. (2011) Robust mediation analysis with missing data and auxiliary variables.

**See Also**

[bmem](#), [bmem.sobel](#), [bmem.plot](#)

---

bmem.sobel.ind	<i>Mediation analysis using sobel test for one indirect effect</i>
----------------	--

---

**Description**

Internal function

**Usage**

```
bmem.sobel.ind(sem.object, ind)
```

**Arguments**

sem.object	A sem object
ind	Indirect effect

**Value**

Internal output

**Author(s)**

Zhiyong Zhang and Lijuan Wang

**References**

Zhang, Z. & Wang, L. (2011) Four methods for mediation analysis with missing data.  
Zhang, Z. (2011) Robust mediation analysis with missing data and auxiliary variables.

**See Also**

[bmem](#), [bmem.sobel](#), [bmem.plot](#)

---

bmem.ssq	<i>Sum square of a matrix</i>
----------	-------------------------------

---

**Description**

Sum square of a matrix

**Usage**

```
bmem.ssq(x)
```

**Arguments**

x	A matrix
---	----------

---

bmem.v	<i>Select data according to a vector of indices</i>
--------	---

---

**Description**

Select data according to a vector of indices

**Usage**

```
bmem.v(x, v, moment = FALSE)
```

**Arguments**

x	A matrix
v	A vector of indices
moment	Covariance analysis or mean and covariance analysis

---

plot.bmem	<i>Plot of the bootstrap distribution</i>
-----------	---

---

**Description**

Plot of the bootstrap distribution

**Usage**

```
## S3 method for class 'bmem'
plot(x, par, ...)
```

**Arguments**

x	A bmem object
par	Name of parameter to be plotted.
...	Options used for the generic plot function.

**Value**

Generate the bootstrap histogram for a chosen parameter.

**Author(s)**

Zhiyong Zhang and Lijuan Wang



**References**

- Zhang, Z. & Wang, L. (2011) Four methods for mediation analysis with missing data.  
Zhang, Z. (2011) Robust mediation analysis with missing data and auxiliary variables.

**See Also**

[bmem](#), [bmem.sobel](#), [bmem.plot](#)

---

popPar

*Get the population parameter values*

---

**Description**

Get the population parameter values including both direct and indirect effects in a model

**Usage**

```
popPar(object)
```

**Arguments**

object            A [lavaan](#) object

---

power.basic

*Conducting power analysis based on Sobel test*

---

**Description**

Different from [power.boot](#), this function conduct power analysis based on the Sobel test.

**Usage**

```
power.basic(model, indirect = NULL, nobs, nrep = 1000, alpha = 0.95,  
skewness = NULL, kurtosis = NULL, ovnames = NULL, se = "default",  
estimator = "default", parallel = "no", ncore = 1, ...)
```

**Arguments**

model	A model specified using lavaan notation and above. See <a href="#">model.syntax</a> for basic model specification. For the power analysis, the population parameter values should be provided in the following way. For example, the coefficient between math and HE is .39. Then it is specified as start(.39). If the parameter will be referred in the mediation effect, a label should be given as a modifier as b*HE+start(.39)*HE. model<- ' math ~ c*ME+start(0)*ME + b*HE+start(.39)*HE HE ~ a*ME+start(.39)*ME ,
indirect	The indirect or other composite effects are specified in the following way indirect<- ' ab: = a*b abc := a*b + c '
nobs	Number of observations for power analysis. If it is a vector, multiple group analysis will be conducted.
nrep	Number of replications for Monte Carlo simulation. At least 1,000 is recommended.
alpha	The alpha level is used to obtain the confidence interval for model parameters.
skewness	A vector to give the skewness for the observed variables.
kurtosis	A vector to give the kurtosis for the observed variables.
ovnames	A vector to give the variable names for the observed variables. This is only needed when the skewness and kurtosis are provided. The skewness, kurtosis and variable names should be in the same order.
se	How to calculate the standard error, for example, robust standard error can be specified using se="robust".
estimator	Estimation methods to be used here.
parallel	Parallel methods, snow or multicore, can be used here.
ncore	Number of cores to be used in parallel. By default, the maximum number of cores are used.
...	Other named arguments for lavaan can be passed here.

**Value**

power	power for all parameters and required ones in the model
coverage	coverage probability
pop.value	Population parameter values
results	A list to give all intermediate results
data	The last data set generated for checking purpose

**Examples**

```
## Not run:
ex1model<- '
math ~ c*ME+start(0)*ME + b*HE+start(0.39)*HE
HE ~ a*ME+start(0.39)*ME
```

```

'
indirect<- 'ab:=a*b'

N<-50

system.time(non.normal<-power.basic(ex1model, indirect, N,
  nrep=2000,parallel='multicore', skewness=c(-.3, -.7, 1.3),
  kurtosis=c(1.5, 0, 5), ovnames=c('ME', 'HE', 'math'), ncore=8))

summary(non.normal)

## End(Not run)

```

power.boot

*Conducting power analysis based on bootstrap***Description**

Different from [power.basic](#), this function conduct power analysis based on the bootstrap method.

**Usage**

```

power.boot(model, indirect = NULL, nobs, nrep = 1000, nboot = 1000,
alpha = 0.95, skewness = NULL, kurtosis = NULL, ovnames = NULL,
ci='default', boot.type='default',
se = "default", estimator = "default", parallel = "no",
ncore = 1, ...)

```

**Arguments**

model	A model specified using lavaan notation and above. See <a href="#">model.syntax</a> for basic model specification. For the power analysis, the population parameter values should be provided in the following way. For example, the coefficient between math and HE is .39. Then it is specified as start(.39). If the parameter will be referred in the mediation effect, a label should be given as a modifier as b*HE+start(.39)*HE. model<- ' math ~ c*ME+start(0)*ME + b*HE+start(.39)*HE HE ~ a*ME+start(.39)*ME ,
indirect	The indirect or other composite effects are specified in the following way indirect<- ' ab: = a*b abc := a*b + c '
nobs	Number of observations for power analysis. If it is a vector, multiple group analysis will be conducted.
nrep	Number of replications for Monte Carlo simulation. At least 1,000 is recommended.
nboot	Number of bootstraps to conduct.

alpha	The alpha level is used to obtain the confidence interval for model parameters.
skewness	A vector to give the skewness for the observed variables.
kurtosis	A vector to give the kurtosis for the observed variables.
ovnames	A vector to give the variable names for the observed variables. This is only needed when the skewness and kurtosis are provided. The skewness, kurtosis and variable names should be in the same order.
se	How to calculate the standard error, for example, robust standard error can be specified using <code>se="robust"</code> .
estimator	Estimation methods to be used here.
parallel	Parallel methods, snow or multicore, can be used here.
ncore	Number of cores to be used in parallel. By default, the maximum number of cores are used.
ci	Type of bootstrap confidence intervals. By default, the percentile one is used. To get the bias-corrected one, use <code>ci='BC'</code>
boot.type	Type of bootstrap method. By default, the nonparametric one is used. Changing it to "BS" to use the Bollen-Stine method.
...	Other named arguments for lavaan can be passed here.

### Value

power	power for all parameters and required ones in the model
coverage	coverage probability
pop.value	Population parameter values
results	A list to give all intermediate results
data	The last data set generated for checking purpose

### Examples

```
## Not run:
ex1model<- '
math ~ c*ME+start(0)*ME + b*HE+start(0.39)*HE
HE ~ a*ME+start(0.39)*ME
'

indirect<- 'ab:=a*b'

N<-50

system.time(boot.non.normal<-power.boot(ex1model, indirect, N,
  nrep=2000, nboot=10000, parallel='multicore', skewness=c(-.3, -.7, 1.3),
  kurtosis=c(1.5, 0, 5), ovnames=c('ME', 'HE', 'math'), ncore=8, ci='percent',
  boot.type='simple'))
summary(boot.non.normal)

## End(Not run)
```

power.curve

*Generate a power curve***Description**

Generate a power curve either based on Sobel test or bootstrap

**Usage**

```
power.curve(model, indirect=NULL, nobs=100, type='basic', nrep=1000,
nboot=1000, alpha=.95, skewness=NULL, kurtosis=NULL, ovnames=NULL,
ci='default', boot.type='default',
se="default", estimator="default", parallel="no",
ncore=1, interactive=TRUE, ...)
```

**Arguments**

model	A model specified using lavaan notation and above. See <a href="#">model.syntax</a> for basic model specification. For the power analysis, the population parameter values should be provided in the following way. For example, the coefficient between math and HE is .39. Then it is specified as start(.39). If the parameter will be referred in the mediation effect, a label should be given as a modifier as b*HE+start(.39)*HE. model<- ' math ~ c*ME+start(0)*ME + b*HE+start(.39)*HE HE ~ a*ME+start(.39)*ME ,
indirect	The indirect or other composite effects are specified in the following way indirect<- ' ab: = a*b abc := a*b + c '
nobs	Number of observations for power analysis. It is typically should be a vector for single group analysis. For multiple group analysis, it should be a matrix.
type	Type of power analysis
nrep	Number of replications for Monte Carlo simulation. At least 1,000 is recommended.
nboot	Number of bootstraps to conduct.
alpha	The alpha level is used to obtain the confidence interval for model parameters.
skewness	A vector to give the skewness for the observed variables.
kurtosis	A vector to give the kurtosis for the observed variables.
ovnames	A vector to give the variable names for the observed variables. This is only needed when the skewness and kurtosis are provided. The skewness, kurtosis and variable names should be in the same order.
se	How to calculate the standard error, for example, robust standard error can be specified using se="robust".
estimator	Estimation methods to be used here.
parallel	Parallel methods, snow or multicore, can be used here.

<code>ncore</code>	Number of cores to be used in parallel. By default, the maximum number of cores are used.
<code>ci</code>	Type of bootstrap confidence intervals. By default, the percentile one is used. To get the bias-corrected one, use <code>ci='BC'</code>
<code>boot.type</code>	Type of bootstrap method. By default, the nonparametric one is used. Changing it to "BS" to use the Bollen-Stine method.
<code>interactive</code>	Whether to get the figure interactively.
<code>...</code>	Other named arguments for lavaan can be passed here.

### Value

<code>power</code>	power for all parameters and required ones in the model
<code>coverage</code>	coverage probability
<code>pop.value</code>	Population parameter values
<code>results</code>	A list to give all intermediate results
<code>data</code>	The last data set generated for checking purpose

### Examples

```
## Not run:
ex2model<-'
ept ~ start(.4)*hvltt + b*hvltt + start(0)*age + start(0)*edu + start(2)*R
hvltt ~ start(-.35)*age + a*age + c*edu + start(.5)*edu
R ~ start(-.06)*age + start(.2)*edu
R =~ 1*ws + start(.8)*ls + start(.5)*lt
age ~~ start(30)*age
edu ~~ start(8)*edu
age ~~ start(-2.8)*edu
hvltt ~~ start(23)*hvltt
R ~~ start(14)*R
ws ~~ start(3)*ws
ls ~~ start(3)*ls
lt ~~ start(3)*lt
ept ~~ start(3)*ept
'

indirect<-'ind1 := a*b + c*b'

nobs <- seq(100, 2000, by=200)

power.curve(model=ex2model, indirect=indirect, nobs=nobs,
type='boot', parallel='multicore', ncore=60, ci='percent',
boot.type='simple', interactive=F)

## End(Not run)
```

---

summary.bmem	<i>Calculate bootstrap confidence intervals</i>
--------------	---

---

**Description**

Calculate bootstrap confidence intervals

**Usage**

```
## S3 method for class 'bmem'
summary(object, ci='bc', cl=.95, ...)
```

**Arguments**

object	An output object from the function <a href="#">bmem</a>
ci	norm: normal approximation CI, perc: percentile CI, bc: bias-corrected CI, bca: BCa
cl	Confidence level. Can be a vector.
...	other options can be used for the generic summary function.

**Details**

The other type of confidence intervals can be constructed from the output of the function [bmem](#). Note if the BCa is required, the ci='BCa' should have been specified in the function [bmem](#).

**Value**

The on-screen output includes the parameter estimates, bootstrap standard errors, and CIs.

---

summary.power	<i>Organize the results into a table</i>
---------------	--

---

**Description**

This function is adapted from the [lavaan](#) summary function to put the results in a table.

**Usage**

```
## S3 method for class 'power'
summary(object, ...)
```

**Arguments**

object	Output from the function either <a href="#">power.basic</a> or <a href="#">power.boot</a> .
...	Other options

# Index

## \* **bmem**

- [bmem-package](#), 3
- [bmem](#), 3, 4, 5, 20–23, 25, 31
- [bmem-package](#), 3
- [bmem.bs](#), 4
- [bmem.ci.bc](#), 5, 7–9
- [bmem.ci.bc1](#), 6
- [bmem.ci.bca](#), 6, 7, 8, 9
- [bmem.ci.bca1](#), 7
- [bmem.ci.norm](#), 6, 7, 8, 9
- [bmem.ci.p](#), 6–8, 9
- [bmem.cov](#), 9
- [bmem.em](#), 10
- [bmem.em.boot](#), 10
- [bmem.em.cov](#), 11, 22
- [bmem.em.jack](#), 7, 12
- [bmem.em.rcov](#), 12
- [bmem.list](#), 13
- [bmem.list.boot](#), 14
- [bmem.list.cov](#), 14, 22
- [bmem.list.jack](#), 7, 15
- [bmem.mi](#), 15
- [bmem.mi.boot](#), 16
- [bmem.mi.cov](#), 16, 22
- [bmem.mi.jack](#), 7, 17
- [bmem.moments](#), 17
- [bmem.pair](#), 18
- [bmem.pair.boot](#), 18
- [bmem.pair.cov](#), 19, 22
- [bmem.pair.jack](#), 7, 19
- [bmem.pattern](#), 11, 20
- [bmem.plot](#), 5, 20, 20, 21–23, 25
- [bmem.raw2cov](#), 21
- [bmem.sem](#), 21
- [bmem.sobel](#), 5, 20–22, 22, 23, 25
- [bmem.sobel.ind](#), 23
- [bmem.ssq](#), 23
- [bmem.v](#), 24
- [lavaan](#), 25, 31
- [model.syntax](#), 26, 27, 29
- [plot \(plot.bmem\)](#), 24
- [plot.bmem](#), 24
- [popPar](#), 25
- [power.basic](#), 25, 27, 31
- [power.boot](#), 25, 27, 31
- [power.curve](#), 29
- [sem](#), 4, 5, 10–19, 22
- [summary \(summary.bmem\)](#), 31
- [summary.bmem](#), 31
- [summary.power](#), 31